

AgilePoint Server Administrator's Guide

AgilePoint BPMS v5.0 R2

Document Revision r5.3.11

June 2014

Contents 2

Contents

Preface	5
Disclaimer of Warranty	5
Copyright	
Trademarks	5
Government Rights Legend	5
Virus-free software policy	
Document Revision Numbers	
AgilePoint Documentation in PDF and HTML	
Opening the Documentation Library	
Finding Information in the Documentation Library	
Downloading Files and Sharing Links from the Documentation Library	
Contacting AgilePoint Sales	
Contacting Customer Support	······································
AgilePoint Server	9
Deploying an AgilePart to AgilePoint Server	10
Checking the AgilePoint Server log files	11
Restarting AgilePoint Server in Windows Service Mode	12
Scheduling an AgilePoint Server Restart in Windows Service Mode	12
Safely Stopping AgilePoint Server in IIS Mode	14
Configuration Settings	15
Configuring an SMTP Account	15
Implementing a Custom Email Notification Delivery Module	
Configuring the AgilePoint Server Thread Pool Size	
Thread Pool Sizing Guidelines	
Increasing Thread Pool Size	
Decreasing Thread Pool Size	
Configuring the Max Loop	
Configuring the Swap Out Time	
Configure Session State Handling	20
AgilePoint Server Configuration Utility	22
System Window	
System Settings	23

	Email Notification Settings	∠3
	Database Window	
	Configuring Process Archiving	
	Extension Window	
	ADSyncModule Extension	
	DBSyncModule Extension	
	Email Approval Extension	
	Enterprise Social AgileConnector	
	ContentListener AgileConnector	
	DataService AgileConnector	
	EventService AgileConnector	69
	Lync Approval AgileConnector	
	MSMQ AgileConnector	
	MSWFRuntime AgileConnector	
	RemotingService AgileConnector	75
	SAP Integration AgileConnector	
	Configuring the AgilePoint SharePoint Integration AgileConnector	
	SMS Service and Approval AgileConnector	
	Configuring the SPSyncModule Extension	
	Yammer Hashtag AgileConnector	94
	Work Calendar Window	
	AgilePoint Server Manager Configuration in Windows Service Mode	104
Ag	gilePoint Deployment Services	
	AgilePoint Deployment Service	
	AgilePoint Deployment Utility	
	Opening the AgilePoint Deployment Utility	
	Adding an AgilePoint Server	
	Removing an AgilePoint Server	
	Backing up a Process Model and Associated Dependencies	
	Restoring a Process Model and Associated Dependencies	
	Migrating a Process Model and Associated Dependencies	
	Rolling back a Process Model and Associated Dependencies	
	Creating a Project	
	Project Functions	
	Opening a Project	
	Saving a Project	
	Packaging a Project	110
	Deleting a Project or Project Collection	
	Closing Projects	
	Deploying a Project	
	Viewing Deployment History	111
	wile Deut Deutschmand MC I 110224	4.4
Ag	gilePart Deployment Wizard Utility	112
_		
۲e	erformance Tracing Utility	113
AP	PADM Command Line Utility	
	APADM Archive Database Command	110

APADM Synchronize Active Directory Command	120
APADM Bulk Migration Command	120
AgilePoint Server Monitor Service	121
AgilePoint Server Manager (Windows Service Environments)	122
Adding a Server Instance	
Deleting a Server Instance	127
Starting a Server Instance	128
Stopping a Server Instance	128
Configuring a Server Instance	128
Managing a Server Instance	128
Running the SVC Client Utility Tool	128
Enabling SSL in AgilePoint Server Manager	
Creating a Self-signed SSL Certificate	131
Binding the SSI Certificate to AgilePoint Server Port	132

Preface

Disclaimer of Warranty

AgilePoint, Inc. makes no representations or warranties, either express or implied, by or with respect to anything in this document, and shall not be liable for any implied warranties of merchantability or fitness for a particular purpose or for any indirect, special or consequential damages.

Copyright

Copyright © 2013 AgilePoint, Inc. All rights reserved.

Trademarks

AgilePoint, Inc. and AgilePoint's products are trademarks of AgilePoint Inc. References to other companies and their products use trademarks owned by the respective companies and are for reference purpose only.

Government Rights Legend

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the applicable license agreement and as provided in DFARS 227.7202-1(a) and 227.7202-3(a) (1995), DFARS 252.227-7013(c)(1)(ii) (Oct 1988), FAR 12.212(a) (1995), FAR 52.227-19, or FAR 52.227-14, as applicable.

Virus-free software policy

AgilePoint recognizes that viruses are a significant security consideration for our customers. To date, we have had no report of AgilePoint BPMS carries any virus. AgilePoint takes the following measures to ensure our software is free of viruses upon delivery:

- AgilePoint is built on top of Microsoft .NET framework. The pre-compiled executable is a.NET Common Language Runtime (CLR) application, not a native machine binary. As far as is known at this time, there are no viruses that infect .NET CLR executables.
- The virtual environment for the product packaging process in is fully isolated and protected, and anti-virus software is installed and running during packaging.
- The deliverable package is scanned by anti-virus software before upload to our customer download site.

Document Revision Numbers

AgilePoint documentation uses the revision number format **rX.Y.Z.** The letters and numbers in this revision number can be interpreted as follows:

- r Indicates "revision." This helps to differentiate the document *version* numbers, which start with v.
- X The major version number for AgilePoint BPMS to which this document refers. For example, AgilePoint releases 5.0, 5.0 SP1, and 5.5 would all have an X value of 5.
- Y- The major document revision number. This number typically changes only when either there is a new AgilePoint release, or there are major changes to the document.
- Z- The minor document revision number. This number is incremented each time the document is republished.

AgilePoint Documentation in PDF and HTML

AgilePoint documentation is provided in both print-friendly (PDF) and web-based (HTML) formats.

Advantages of HTML Documentation

- HTML is the primary delivery format for AgilePoint documentation.
- Unified, global search across all documentation. PDF documents allow you to search only within the context
 of a given PDF file.
- All hyperlinks supported. Links in PDFs are only supported in certain contexts.
- "One-stop shopping" for all information related to AgilePoint BPMS.
- The HTML documentation is updated more frequently than the PDF documentation. Web-based documentation is updated periodically between AgilePoint releases to address errors and omissions, but the PDF documentation is updated only at the time of a software release.

Advantages of PDF Documentation

PDFs can be more easily **printed**, **archived**, and **transferred** (such as by FTP or email) than HTML documentation.

For more information, see Downloading Files and Sharing Links from the Documentation Library in the Documentation Library.

Opening the Documentation Library

To open the AgilePoint Documentation Library, do the following.

Prerequisites

You must have a valid account on the AgilePoint Support Portal.

Instructions

- 1. Log on to the AgilePoint Support Portal.
- 2. Click Documentation.
- 3. On the **Documentation** page, click the documentation library for your AgilePoint release.
 - For AgilePoint BPMS v5.0 SP1 and higher, the web-based documentation library opens in a new tab or window in your web browser.

 For releases prior to v5.0 SP1, a download starts for a Zip file with the PDF documentation for your release.

Finding Information in the Documentation Library

The information in this topic will help you to locate information in the AgilePoint Documentation Library.

Using the Table of Contents

The table of contents in the AgilePoint Documentation Library is divided by content areas. For example, the Installation section includes all the information you need to install AgilePoint BPMS. The AgilePoint API section includes information about the AgilePoint APIs.

You can use the Table of Contents to explore the AgilePoint documentation content and find the information you want.

Searching

The web-based documentation includes a centralized search for all documentation content. To search for information:

1. In the AgilePoint Documentation Library, click the **Search** tab. In the Search box, enter **1 search team**, and click **Search**.

The search results display in alphabetical order by topic title.

It is important to understand that the third-party software AgilePoint uses to generate web-based documentation allows only 1 search term. More than 1 search term will cause the search to fail.

AgilePoint recommends using a relatively unique search term to find the information you need. For example, entering a common term, such as "process," will return a high percentage of the total documentation topics in the search results.

2. Browse the list of topic titles to find the information you want.

Printing

The PDF documentation is provided mainly for the purpose of printing and archiving. To print a set of information:

- Navigate to the main page of the Documentation Library from which you want to print.
- 2. In the list of documents, click the document name in the **PDF** column.
- 3. From your PDF reader software, print the portion of the document you want.

Downloading Files and Sharing Links from the Documentation Library

You can download and share files AgilePoint's documentation library as you would in any other web page. Note that if you send links to recipients, they must have a Support Portal login to view the file.

These procedures are common examples based on Internet Explorer with the Adobe Reader plug-in. Exact procedures may vary depending on your web browser, PDF viewer, and email client configuration.

Share a Link to an HTML Topic

- Navigate to the topic you want to share.
- 2. Copy the URL in the Location box in your web browser.
- 3. Paste the URL in an email, IM client, etc.

Share a Link to a PDF Document

- 1. In Internet Explorer, navigate to the Documentation Library home page.
- 2. In the PDF column, right-click the name of the PDF file you want to share.
- 3. In the quick menu, click Copy shortcut.
- 4. Paste the URL in an email, IM client, etc.

Save a Copy of a PDF Document

- 1. In Internet Explorer, open the Documentation Library home page.
- 2. In the **PDF** column, click the name of the PDF file you want to share.
- 3. In the Adobe Reader plug-in, click **Save** button.

Contacting AgilePoint Sales

AgilePoint is a leading Business Process Management System (BPMS) provider created by a team of driven people who strive to incorporate the principles of relentless innovation for the benefit of our customers. Our mission is to help companies of any size attain and sustain operational success through process excellence.

Headquarters: AgilePoint Corporation 1916C Old Middlefield Way Mountain View, CA 94043, USA

Tel: (650) 968 - 6789 **Fax:** (650) 968 - 6785

Email: info@agilepoint.com

Web site: www.agilepoint.com

International: For AgilePoint EMEA and AgilePoint Asia Pacific, please call the AgilePoint Corporate Office for

contact information.

Contacting Customer Support

To contact AgilePoint Support, please submit a ticket on the AgilePoint Support Portal: http://support.agilepoint.com/SupportPortal/

If you do not have a Support Portal account, you can send an email to request one: support@agilepoint.com

AgilePoint Server 9

AgilePoint Server

AgilePoint Server is the server-side software engine that runs your AgilePoint-based processes. AgilePoint Server interprets the XML schema associated with a process and programmatically executes the appropriate actions. AgilePoint Server's SOA-based software model is what enables you to create and run processes without writing software code.

This document is a user's guide and reference to the features, functionality, usage, configuration, and administration of the AgilePoint Server component of the AgilePoint BPMS Suite.

Deploying an AgilePart to AgilePoint Server

To deploy an AgilePart to AgilePoint Server, use the AgilePoint Deployment Wizard utility. For more information, see AgilePart Deployment Wizard Utility in the Documentation Library.

Checking the AgilePoint Server log files

AgilePoint Server creates and maintains log files to store certain informational, warning, and/or error messages about the server and the workflow engine. These log files are created automatically, and named based on the date and time each file was created.

To enable AgilePoint Server debug mode, you must modify the "netflow.cfg" file located in the AgilePoint Server directory (e.g. [AgilePoint Server installation folder] or "C:\Inetpub\wwwroot\AgilePointServer\").

Add the debug attribute to the server element in the "netflow.cfg" file (as shown below):

```
<server
   eventCap="50"
   workingCap="50"
   maxLoop="50"
   swapoutTime="60"
   debug="true"
   archiveTime="180"
   assemblyPath="C:\Inetpub\AgilePointSite\TuscaSampleApplication\bin">
```

To access the logs, simply view the relevant file(s) using a text editor. The files are located within your AgilePoint Server folder at:

...\AgilePointServer\log*.*

Restarting AgilePoint Server in Windows Service Mode

To restart AgilePoint Server running in Windows Service mode, do the following.

Prerequisites

Microsoft Windows PowerShell is installed on your machine.

Navigation

1. Open the Windows PowerShell utility.

Instructions

- 1. At the PowerShell command prompt, enter the following commands, as appropriate for your system:
 - a. If you are using AgilePoint Clustering Server Manager (NLB environment), enter the following:

```
Restart-Service [Cluster Server Manager service name]
```

b. To restart AgilePoint Server, enter the following:

Restart-Service [AgilePoint Server Manager service name]



Note: In an NLB environment, AgilePoint recommends restarting the servers on different days to maintain system availability. If you restart them on the same day, it is possible to experience system downtime.

Scheduling an AgilePoint Server Restart in Windows Service Mode

To restart AgilePoint Server running in Windows Service mode based on a schedule, do the following.

Prerequisites

Microsoft Windows PowerShell is installed on your machine.

Navigation

Open Notepad.

Instructions

1. In NotePad, create a new file with the following command, and save it as a PowerShell script file with a name such as apserverrestart.ps1:

```
Restart-Service [AgilePoint Server Manager service name]
```

If you have multiple AgilePoint Server service instances, create a separate script file for each instance.

2. If you have an NLB environment, in NotePad, create a new file with the following command, and save it as a PowerShell script file with a name such as **csmrestart.ps1**:

```
Restart-Service [Cluster Server Manager service name]
```

3. In Notepad, create a new file with the following command, and save it as a batch file with a name such as apserverrestart.bat:

```
PowerShell -command "& '[path]\apserverrestart.ps1' "
```

If you have multiple AgilePoint Server service instances, create a separate script file for each instance.

4. If you have an NLB environment, in Notepad, create a new file with the following command, and save it as a batch file with a name such as **csmrestart.bat**:

```
PowerShell -command "& '[path]\csmrestart.ps1' "
```

5. Use Windows Scheduler to execute the batch files according to the schedule you want.



Note: In an NLB environment, AgilePoint recommends restarting the servers on different days to maintain system availability. If you restart them on the same day, it is possible to experience system downtime.

Safely Stopping AgilePoint Server in IIS Mode

To stop (or shut down) AgilePoint Server in IIS mode safely (i.e. without risking any data loss for requests currently being processed), please use the following instructions.

Whenever you are performing maintenance on a resource required to run AgilePoint Server (e.g. taking the workflow DB offline, upgrading AgilePoint Server, etc.), it is recommended that you first stop AgilePoint Server. This will prevent possible problems, such as: data loss; email notification errors; etc.

- 1. (Optional) If you are using the AgilePoint Server Monitor windows service, it is recommended that you stop the service while AgilePoint Server is unavailable.
- 2. Open the IIS management console.
- 3. Under your server's Application Pools node, select the application pool associated with your AgilePoint Server application.
- Stop the application pool (e.g. by right-clicking and choosing **Stop**).
 You can also choose Recycle if you want the AgilePoint Server application to be available again immediately.
- 5. When you are ready, start the application pool to make the AgilePoint Server application available again.

Configuration Settings

This section describes additional AgilePoint Server Configuration Settings that can be implemented via AgilePoint Server's configuration file (i.e. netflow.cfg). This file is located in the [AgilePoint Server installation folder]. These additional configuration options are done manually, as currently there is not a user interface to support them.

Configuring an SMTP Account

By default, AgilePoint Server uses anonymous SMTP. To configure your SMTP server to require authentication, do the following.

Navigation

1. In a text editor, open the AgilePoint Server configuration file netflow.cfg from the following location:

```
[AgilePoint Server installation folder]\netflow.cfg
```

Instructions

 In netflow.cfg in the notification node, enter the email address and password in the smtpService attribute as follows:

```
<notification
   mode="[true or false]"
   format="[text or html]"
   smtpService="[smtp service assembly name]:[smtp service
        class name]:[email address],[password]"
   mailServer="[SMTP server host name]:[port number]:ssl"
   sender="[sender email address]"
   sysadm="[AgilePoint administrator email address.
        If blank, the system uses the sender email address.]"
   encoding="[encoding format]"</pre>
```

Example:

```
<notification
    mode="true"
    format="text"
    smtpService="Builtin::username@sbcglobal.net,mypassword"
    mailServer="smtp.sbcglobal.yahoo.com"
    sender="apnotifier@mycompany.com"
    sysadm="adminuser@mycompany.com"
    encoding="utf-8"</pre>
```



Note: It is not required to add the user name/password to AgilePoint as a registered user.

Implementing a Custom Email Notification Delivery Module

By default, AgilePoint uses System.Web.Mail for the Email Delivery Module. However, System.Web.Mail sometimes may not work as well with some SMTP servers. AgilePoint provides the flexibility to allow you to plugin your own email delivery module or use a third-party component for the email delivery.

To plug-in your own mail delivery module:

1. First, implement the interface IWFSMTPService:


2. Add your assembly and class information into the AgilePoint Server configuration file (netflow.cfg). For example:

Where **EasyMailForSMTP** is the assembly name and **CustomSMTP.EasyMailForSMTPService** is the class name.

Configuring the AgilePoint Server Thread Pool Size

The **System** tab of the AgilePoint Server Configuration utility provides the user interface to configure the maximum number of threads that AgilePoint will be able to use at runtime while handling workflow requests. When the thread pool is configured via this utility it sets both the Event Capacity (for processing AgileWorks) as well as the Working Capacity (for processing AgileParts). In most cases, the same thread pool size as configured via the utility is sufficient for both the Working Capacity as well as the Event Capacity.

For thread pool sizing, anything between 10-100 should be fine. In most cases, a thread pool size of 10 provides a good balance between concurrent processing and server resource optimization.



In some cases, additional tweaking of thread pool sizing may improve performance when heavy CPU usage is apparent for processing AgileParts versus AgileWorks. This finite control over thread pool sizing can be accomplished via the AgilePoint Server Configuration file (i.e., netflow.cfg).

As stated above, when using the AgilePoint Server Configuration utility to set the Thread Pool Size, the value entered, sets both the Event Capacity (for processing AgileWorks) as well as the Working Capacity (for processing AgileParts). However, manual customization can be done via the netflow.cfg to adjust the Working Capacity for a thread pool without changing the Event Capacity or vice versa. For example, if your CPU is processing a large number of AgileParts rather than AgileWorks, you may want to increase the Working Capacity thread pool size, and leave the Event Capacity as is. Improving AgilePart performance is the key to improving capacity because AgilePart processing can cause a bottleneck.

To modify the netflow.cfg file for thread pool optimization, follow these steps.

- Open the netflow.cfg file and locate the server eventCap and workingCap attributes.
- 2. Increase the **eventCap** number to increase the available threads for processing AgileWorks or increase the **workingCap** to increase the number of threads for processing AgileParts. The results are viewed via Enterprise Manager on the Performance page.

Thread Pool Sizing Guidelines

When configuring thread pool size, bigger is not always better! More concurrently running threads requires more server resources (e.g. RAM and CPU), so increasing the thread pool size past a certain point could start to decrease performance rather than improve it. In most cases, a thread pool size of 10 provides a good balance between concurrent processing and server resource optimization. Anything between 10-100 should typically be fine for the Thread Pool. Also, it is often just as (if not more) important to configure the IIS App Pool Queue Length Limit appropriately as to fine tune the Thread Pool size.

If all of your process' activities are "short-duration" ones, then you may not need many threads, because the only way that "short-duration" activities alone would typically cause AgilePoint to (simultaneously) utilize the maximum number of threads in the Thread Pool is if a large number of such activities were entered/activated nearly simultaneously. However, if you have a mixture of "long-running" activities and "short-duration" activities, then increasing thread pool sizes may help considerably because "short" activities that start in the "middle" of a long running activity will not have to wait for it to end before being processed. In general, if you analyze a given time period, then increasing either the quantity or the average duration of activities that are active within that time period will increase the likelihood that some of those activities will require concurrent processing (and therefore require a larger Thread Pool size). However, in certain environments, usage patterns may also have a significant affect, and may render some of the above guidelines less (or more) accurate.

In the above context, a "long-running" activity is defined as one that will require server resources for a length of time long enough that it may overlap with other/subsequent activities or processing. Examples of long running activities could include: synchronous AgileParts that require several minutes (or even hours) of processing to complete; Web Service activities with a large timeout value; AgileShapes that interact with (and may have to wait for data from) other servers or systems; etc.

Conversely, a "short-duration" activity is one that will only consume server resources for a brief period. Examples of such activities include: AgileParts that perform minimal processing; Manual activities (or AgileWorks that perform minimal server-side processing); Single- or Multiple-Condition AgileShapes; etc. Note that Manual activities are normally considered to be "short-duration" activities regardless of the activities' time span or due date, because the AgilePoint server's resources are not being used during most of the activities' duration.

Another way to consider the issue is to determine how frequently new processes will be initiated/launched, how long each process takes to complete, and how much of that time is spent on "automatic" activities that are performed by the server. If you have many long-running processes running simultaneously, and each one contains automatic activities that require minutes (rather than seconds or microseconds) to complete, then you are much more likely to have simultaneous workflow processing occurring, which would require more threads for optimal performance.

See below for a list of guidelines that should be helpful in determining a good Thread Pool size for most environments.

Increasing Thread Pool Size

It may help to increase the Thread Pool size if:

- The average server-side processing duration for activities increases.
- The number of activities entered/activated per day increases.
- The number of new process instances per day increases (because this will typically increase the number of activities entered/activated per day).
- The average number of activities per running process instance increases (i.e. if you start deploying much more complicated process models than you were, it increases the likelihood of concurrent processing).
- The average duration (from Start to Complete) of your process instances increases (because this may increase the number of activities entered/activated per day). This is especially true for processes whose duration is determined by the number of times the process instance "loops" back and re-enters an activity earlier in the process model. It may not be relevant for processes whose duration is primarily determined by the durations of the Manual activities in the process.
- Any of your commonly-used processes contain activities that require minutes (or longer) of server-side processing (as described above), as this significantly increases the likelihood of concurrent processing.
- Your environment is prone to intermittent periods of much-higher-than-average load during certain times of day (or week, month, etc.). For example, if your process instances are often started nearly simultaneously (e.g. at the start of the work day or shift, or because of certain events like the upload of a large batch of

files), or you have many activities that "time out" simultaneously (e.g. at the end of the month), then it may make sense to increase the Thread Pool size to take the higher-load periods into account.

- Your server, network, or database is prone to intermittent "slowdowns" (i.e. periods of slower-than-normal processing). E.g. This could be due to scheduled services running in the background at specified times of the day, or could be caused by periods of high server load caused by non-AgilePoint sites or applications (on a non-dedicated server).
- Your server has plenty of memory (i.e. RAM), but not a lot of processing speed (i.e. CPU speed). In other
 words, activities will take longer to process on a slow machine.

Decreasing Thread Pool Size

It may help to decrease the Thread Pool size if:

- Your server has limited memory (i.e. RAM). Regardless of CPU speed, a server with limited RAM should limit the amount of concurrent processing performed (i.e. threads used) in order to limit memory usage.
- All (or almost all) of your processes use only short-duration activities. In such a scenario, it may be faster
 for the server to process all activities sequentially (more or less) using a small number of threads, than to
 concurrently process the same activities. In such a scenario, the server resources required in order to split
 the server's CPU cycles between multiple threads may actually be (slightly) slower than simply waiting for
 any activities currently being processed to be completed.
- The opposite of any of the items in the previous list is true. However, note that decreasing the Thread Pool size will rarely result in dramatic performance improvements, so you typically don't need to fine-tune the Thread Pool size below 50.

Configuring the Max Loop

The Max Loop is the number of times a process instance can loop back to the previous step. The maximum number of sessions for an activity is set to **50** by default. Once a process instances loops back the 51st time, the process instance will become suspended.

Instructions

In some cases, you may have a special need to have more than 50 sessions, in this case, open the **netflow.cfg** file in Notepad, and change the value for **maxLoop** to a higher value, and then save the file.

Reset IIS upon making changes to the netflow.cfg file.

You can also set the Maxloop at the process model level to avoid an infinite loop scenario. The process level MaxLoop setting overwrites the global/server level setting in the netflow.cfg file.

There is a Process Template property in AgilePoint Envision called 'Maximum Session Allowed' that allows for the configuration of MaxLoop that will overwrite the global/server level setting in the netflow.cfg file.

Configuring the Swap Out Time

The Swap Out Time configuration option refers to the maximum amount of time a process instance remains in idle before it is swapped out of memory. The maximum swap out time is set to 5 minutes (300 seconds) by default. Increasing the swap out time lets the process stay in memory longer, avoiding the CPU intensive swapping, but keep in mind this may eventually affect capacity. Because swapping consumes a lot of CPU time, it may be beneficial to reduce this number if the CPU is low on memory to improve performance.

To change this setting, open the file [AgilePoint Server installation folder]\netflow.cfg in Notepad, change the value for swapoutTime to a higher/lower value depending on the needs, then save the file. (Any changes to netflow.cfg require an IISReset in order to take effect.)

Adjusting the swap out time should only be a temporary workaround solution. If performance is an issue, investing in another CPU, more memory, or a faster hard drive, is a better solution.

Configure Session State Handling

After installing AgilePoint Server and Enterprise Manager, you must configure session state handling. There may be several valid options, depending upon your environment and your organization's requirements.

Value	Description		
InProc	This is the default value for ASP.NET. This value is suitable for single-machine AgilePoint Server environments; you cannot use this setting for NLB.		
StateServer	This setting can be used in a single-machine or NLB environment to manage the session state using the ASP.NET State Service Windows Service. To use the StateServer setting, the ASP.NET State Service must be running on a separate machine from AgilePoint Server.		
SQLServer	In NLB environments, this setting allows the AgilePoint Servers to store their session data on a separate machine in a SQL Server database. If an AgilePoint Server fails, another server in the cluster can take over and serve requests with session data loss.		
Off	This setting enables you to turn off the session state for AgilePoint Server. This setting can help to improve performance of AgilePoint Server in NLB environments. You cannot use this session for Enterprise Manager.		
Custom	This setting requires custom coding. For more information, contact AgilePoint Support.		

If you use Session State handling in an NLB environment, note the following:

- The session must be persisted outside of the current server.
- This session persistence is managed by the .NET Framework, not by AgilePoint. The framework uses the connection string declared in the web.config for AgilePoint Server and AgilePoint Enterprise Manager. See http://msdn2.microsoft.com/en-us/library/87069683(vs.71).aspx to communicate to the database where the session is persisted.

To set up session state handling:

- Run InstallSqlState.sql (installed by default in [system root]\Microsoft.NET\Framework\version) on the
 computer running SQL Server that will store the session state (i.e. the db server). This creates a database
 called ASPState with new stored procedures and ASPStateTempApplications and ASPStateTempSessions
 tables in the TempDB database.
- 2. Open the **AgilePoint Server** and **AgilePoint Enterprise Manager web.config** files. In the <sessionState> node, set the values as required for your environment.

For example, if you are using the **SQLServer** setting, the SQL connection string must point to the session state SQL Server database on the DB server machine that stores the session data:

<sessionState mode="SQLServer"</pre>

```
sqlConnectionString="[your sessionState database connection string]"
cookieless="false"
timeout="20000"
/>
```

If you are using the **Off** setting, no further information is required:

<sessionState mode="Off" />


AgilePoint Server Configuration Utility

The AgilePoint Server Configuration utility can be accessed via: **Start > All Programs > AgilePoint > AgilePoint Server Configuration**.

This utility is a user-friendly editor for AgilePoint Server's **netflow.cfg** configuration file. This file can be found in the root folder where you have installed AgilePoint Server (e.g. c:\inetpub\wwwroot\AgilePointServer \netflow.cfg). The location of AgilePoint Server can be determined from the registry.

Although most of the AgilePoint Server configuration settings can be managed via the AgilePoint Configuration Utility, there are some additional configuration settings that can be modified manually via the netflow.cfg file.

For more information, see Configuration Settings in the Documentation Library.



System Window

This window allows you to configure the AgilePoint system user, thread pool sizing, and default email notification settings.

System Settings

The System area allows you to specify the identity and authentication information for the AgilePoint system user, and the maximum number of threads that AgilePoint will be able to use at run time while handling workflow requests.

The **System User** and **Password** fields should contain the same values that you would use when logging into Windows. However, if you are installing AgilePoint Server on a Windows Server that is a Domain Controller, you cannot use a local administrator account as the AgilePoint Server System User, because the domain controller will not recognize local accounts. To successfully configure AgilePoint Server on a Windows Server domain controller, check the Active Directory check box, and specify the domain name and administrator account that belongs to the domain controlled by the domain controller.

For thread pool sizing, anything between 10-100 should be fine. In most cases, a thread pool size of 10 provides a good balance between concurrent processing and server resource optimization.



Note: In some cases, additional tweaking of thread pool sizing may improve performance when heavy CPU usage is apparent for processing AgileParts versus AgileWorks. This finite control over thread pool sizing can be accomplished via the AgilePoint Server Configuration file (i.e. netflow.cfg). For more information, see Configuring the AgilePoint Server Thread Pool Size in the Documentation Library.

Email Notification Settings

The Notification area allows you to specify the default values for the email notification settings.

AgilePoint Server's notification mechanism uses an extensible framework that allows for the creation of custom notification modules. AgilePoint server provides a built-in notification module as default. However, it is possible to replace AgilePoint's default module with a custom notification module so that all AgilePoint notifications are processed and sent using the custom module. This allows you to implement virtually any kind of custom notification scenario, including IM, email "batch sending", sending via custom APIs, etc.


For more information, see Implementing a Custom Email Notification Delivery Module in the Documentation Library.

Database Window

This window allows you to configure the workflow database that AgilePoint Server will use to store data. AgilePoint supports the following database types:

- Microsoft SQL Server (Recommended because of additional reporting integration features.)
- Oracle

It is recommended to use a connection pool size that is >= 100 or 2 * the thread pool size.



Configuring Process Archiving

Process archiving moves a process instance and all its related data to an archive database when the Completed or Canceled date for the process instance exceeds a specified number of days. This helps save storage space on the main AgilePoint database and improve performance.

You can also archive process data manually. For more information, see APADM Archive Database Command in the Documentation Library.

Prerequisites

Create a database to use as the archive database.

Navigation

- 1. Log on to Windows using a user account with the access rights "Archive Process Instance" in AgilePoint.
- 2. Open the AgilePoint Server Configuration Utility: **Start > All Programs > AgilePoint > AgilePoint Server Configuration**.
- 3. Click the **Database** tab.

Instructions

- 1. In the AgilePoint Server Configuration Utility On the **Database** tab, click the **Archive Database** tab.
- In the Authentication section, configure authentication for the archive database.
- 3. In the **Database Server** field, enter the server name for the archive database.


- 4. In the **Database Name** field, click the ellipses button to populate the database names on the database server.
- 5. In the **Database Name** field, select the name of the archive database.
- 6. In the **Archive completed process in** field, set the number of days to save Completed or Canceled processes before archiving.

The process for archiving AgilePoint processes runs once per day between 1:00 a.m. and 3:00 a.m.

To suspend a database archive schedule without deleting the settings, set Archive completed process in to 0.

Extension Window

AgilePoint provides a powerful integration framework; Global Server Control Extended Module, to allow you to easily extend AgilePoint with additional server control modules. These server control modules extend AgilePoint's functionalities and provide a higher level of customizability. The Extension window allows you to register and configure certain optional server extensions through the Global Server Control Extended Module that can be used to modify the workflow engine's run time behavior. See the sections below for details on the supported extensions.



The Add and Edit buttons allow you to register a new server extension. (See below for details.)

The Remove button allows you to un-register the highlighted server extension.

The Configure button allows you to modify the settings and configuration of the highlighted server extension. It is only enabled for server extensions that support additional configuration options.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

ADSyncModule Extension

For most enterprises, Active Directories are changing continuously with users added or removed frequently. For enterprises with large numbers of groups and users, a mechanism to automate the synchronization of the member association in Active Directory plays an important role for any Active Directory integration.

In addition to the built-in Active Directory integration with products such as: Envision and Enterprise Manager, AgilePoint also provides an out-of-the-box Active Directory synchronization module which can be plugged into AgilePoint through the Global Server Control Module framework. This synchronization module provides the synchronization capability between Active Directory groups and AgilePoint groups automatically.

This synchronization module can be added to the AgilePoint system through the AgilePoint Global Server Control Extended Module. This server extension allows you to enable and configure automated synchronization of the AgilePoint authentication data with Active Directory. It will automate the member synchronization between Active Directory users and groups and AgilePoint users and groups.

Requirements

- The AgilePoint System User (as defined in the AgilePoint Server Configuration utility) should belong to the Active Directory domain.
- AgilePoint Server's Application Pool's Identity user account (as configured in IIS) needs to have read
 permissions to the Active Directory server and data.

Enabling the AdSyncModule Extension

To enable the AgilePoint Server extension:

- 1. Open the AgilePoint Server Configuration utility and go to the **Extension** window.
- 2. On the Extension window, click Add.
- 3. Click the Ellipses button next to the Assembly field and add the following assembly:

...\AgilePointServer\bin\ADSyncModule.dll


4. In the **Impersonator** field, enter the credential for the AgilePoint Service Account.

For more information, see Setting Up the Hosted Service

- 5. Click **OK**. Now you will need to configure the module to schedule the synchronization.
- 6. Click the **Configure** button, and specify the desired configuration settings. In the following configuration interface, you can specify the synchronization with the frequency of every day, week, or month and at a particular time of day starting with the day you set the schedule. The synchronization module also provides the option of registering the users automatically or sending an alert email to AgilePoint system user if there are members in the Active Directory groups that have yet to be registered in AgilePoint.
- 7. Click OK.

Configuration for Active Directory Groups Synchronization Window

Synchronizes AgilePoint Server user data with Active Directory.



Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select ADSyncModule.dll.
- 4. Click Configure.

Field Definitions

Field Name	Definition		
Path	Definition: Specifies the LDAP connection string for your Active Directory.		
	Allowed Values: A valid LDAP connection string. Use the Ellipses button to retrieve the connection string for the current Active Directory. Default Value:		
	LDAP:// Example: LDAP://DC=MyCompany,dc=com		
Domain	Definition: The authentication domain for Active Directory users. Allowed Values: A valid domain. Default Value: None		
AgilePoint System User	Definition: Specifies whether the ADSync module extension connects to the specified Active Directory using the AgilePoint Service Account (or system account). Allowed Values: Selected - The ADSync module uses the AgilePoint Service Account. Deselected - The ADSync module uses a custom account. Default Value: Selected		
Custom Account	Definition: Specifies whether the ADSync module extension connects to the specified Active Directory using a		

Field Name	Definition		
	specified account other than the AgilePoint Service Account. This is useful if the AgilePoint Service Account does not have an account on your Active Directory domain.		
	Allowed Values:		
	Selected - The ADSync module uses a custom account.		
	Deselected - The ADSync module uses the AgilePoint Service Account.		
	Default Value:		
	Deselected		
Username	Definition:		
	Specifies the user name for an account you want AgilePoint Server to use to connect to your Active Directory domain.		
	Allowed Values:		
	A valid user name for an account that has access to the Active Directory domain to which you want to connect.		
	Example:		
	DEMO3/jsmith		
Password	<u>Definition:</u>		
	The password for the authentication account.		
	Allowed Values:		
	A valid password.		
	Default Value:		
	None		
Schedule	Function:		
	The frequency for Active Directory synchronization. Synchronization can occur every day, week, or month, at a particular time or day.		
Disable Email Notification of the Synchronization	Definition:		
Activities	Disables email notifications for Active Directory synchronization.		
	Allowed Values:		

Field Name	Definition		
	Selected - Disables email notifications for Active Directory synchronization.		
	Deselected - Enables email notifications for Active Directory synchronization.		
	Default Value:		
	Deselected		
If Active Directory group member is not AgilePoint user	Definition:		
	Specifies what actions to take if a member of your Active Directory is not a registered AgilePoint user.		
	Allowed Values:		
	Register user to AgilePoint automatically Creates an AgilePoint account for the user using their Active Directory information.		
	 Send email to AgilePoint system user, and do not take any action - Does not create an AgilePoint account for the Active Directory user, but sends a notification email to the AgilePoint system user account. 		
	Default Value:		
	Register user to AgilePoint automatically		
Sync all Lync IDs with email IDs	Definition:		
	Synchronizes all of your users' Lync IDs with their email IDs.		
	This synchronization occurs each time and Active Directory synchronization occurs. AgilePoint recommends using this option only if all of your users' messaging IDs and email IDs are the same.		
	Allowed Values:		
	Selected - Synchronizes Lync IDs with users' email IDs.		
	Deselected - Does not synchronize Lync IDs with users' email IDs.		
	Default Value:		
	Deselected		
Sync all Yammer IDs with email IDs	Definition:		
	Synchronizes Yammer IDs with AgilePoint users' email IDs. This synchronization occurs each time and Active Directory synchronization occurs. AgilePoint recommends using this option only if all		

Field Name	Definition		
	of your users' messaging IDs and email IDs are the same.		
	Allowed Values:		
	 Selected - Synchronizes Yammer IDs with users' email IDs. 		
	 Deselected - Does not synchronize Yammer IDs with users' email IDs. 		
	Default Value:		
	Deselected		

Group Member Synchronization Rules

- Only groups that have already been added into AgilePoint will be synchronized with Active Directory. New
 Active Directory groups will not be added automatically to AgilePoint. The new Active Directory groups can
 be added manually through the Enterprise Manager interface.
- The changes of user members (adding or removing) in the Active Directory groups will be synchronized to AgilePoint but the changes in AgilePoint groups will NOT be synchronized back to the Active Directory.
- The synchronization only applies to member association (Add or Remove) within the groups. Group
 properties such as names and descriptions are NOT synchronized.
 - When a new member is added to Active Directory, this member will also be added to the corresponding AgilePoint group. If the actual user entity is not registered in AgilePoint yet, the user entity will be registered to AgilePoint automatically.
 - When a member is removed from Active Directory, this member in the corresponding AgilePoint group
 will also be removed. The actual user entity will NOT be removed from AgilePoint as the same user
 entity can also be associated with other groups in the system.
 - If the Active Directory contains sub-groups (Nested groups), the members in the sub-groups will also be synchronized and the members will be added to or removed from the top level group.

User Synchronization Rules

- Changes to the following Active Directory User properties will be synchronized to AgilePoint. Other properties will NOT be synchronized.
 - Full Name
 - Email Address
 - Department
 - Title
 - Manager
- Removal of an Active Directory User will result in the following AgilePoint synchronization actions:
 - The user will be removed from any AgilePoint Groups.

 Any tasks assigned to this user will still exist, it may be required to cancel or reassign these tasks to a valid AgilePoint user.

Filtering the ADSyncModule Extension

The Extra Filter feature has been added in the ADSync module using two keys of String data type: RequireExtraFilter and ExtraFilterValue. This feature provides extra filter options to synchronize users between Active Directory and AgilePoint. The RequireExtraFilter key is used to enable the Extra Filter feature. The ExtraFilterValue key stores the extra filter value which is a LDAP query. Do not use the objectcategory or objectclass keywords in the query because these keywords are included in the feature.

Prerequisites

The ADSyncModule extension is enabled.

Instructions

 In the Windows Registry, create the following keys in the location SOFTWARE\Ascentn\Server \ActiveDirectory

Name	Value		
RequireExtraFilter	Definition: Specifies whether additional LDAP filters are required for the Active Directory Sync module. Allowed Values: Yes/True - Enabled No/False - Disabled		
ExtraFilterValue	Definition: Specifies an LDAP query that defines a synchronization filter for Active Directory. Allowed Values: An LDAP query that does not include the objectcategory or objectclass keywords. Example: (mail=*) Synchronizes users who have email IDs. (givenName=John) Finds users with the given name John.		

Synchronizing Active Directory groups with AgilePoint groups

Special characters can be included in group names while synchronizing users of Active Directory and AgilePoint by using a CustomActiveDirectorySync key of String data type in the ADSync module. However, the semicolon (;) and tilde (~) characters cannot be used in group names, because they act as group-pair separators, as follows:

<AgilePointGroup1>~<ActiveDirectoryGroup1>;<AgilePointGroup2>~<ActiveDirectoryGroup2> and so on.

Prerequisites

The ADSyncModule extension is enabled.

Instructions

In the Windows Registry, create the following keys in the location SOFTWARE\Ascentn\Server \ActiveDirectory

Name	Value		
CustomActiveDirectorySync	Definition:		
	The data type is String.		
	Allowed Values:		
	A semicolon-delimited list of group pairs in the following format:		
	<apgroup1>~<adgroup1>;<apgroup2>~<ae< td=""></ae<></apgroup2></adgroup1></apgroup1>		
	Example:		
	<apmygroup>~<adyourgroup></adyourgroup></apmygroup>		
	Specifies that an AgilePoint Group named APMyGroup is to be synchronized with an Active Directory Group named ADYourGroup.		
	APMyGroup>~ <adyourgroup>;<apourgroup< p=""></apourgroup<></adyourgroup>		
	Specifies that 2 pairs of groups are synchronized: APMyGroup with ADYourGroup, and APOurGroup with ADTheirGroup.		

Scheduling

The schedule of the synchronization is set through the module's configuration interface. The synchronization can be performed at a particular time of day with the frequency of every day, every week, or every month.

For example, if you schedule the synchronization to be performed at 2am on Jan. 1 and you also select **Every day** as the frequency, the synchronization will be started automatically at 2am on Jan 1, Jan 2, Jan 3, etc.

The following table summarizes the different ways that the schedule can be set for the synchronization.

Frequency	Time	1st Sync	2nd Sync	3rd Sync	4th Sync	5th Sync
Every Day	2am	Jan. 1	Jan. 2	Jan. 3	Jan. 4	Jan. 5
Every Week	2am	Jan. 1	Jan. 8	Jan. 15	Jan. 22	Jan. 29
Every Month	2am	Jan. 1	Feb. 1	March. 1	April. 1	May. 1

The synchronizations typically happen within five minutes of the scheduled time. For example, if the scheduled time is 2am, the actual synchronization could happen between 1:55am to 2:05am.



Note: The scheduling pattern (daily, weekly, or monthly) and scheduling time should be the same for multiple AgileConnectors of the same type.

Exception Handling

This module also provides exception handling for the scheduling. In the event that your server is down during the scheduled synchronization, as soon as your server is back online, the synchronization will be automatically kicked off. After that, the next synchronization will resume the original schedule.

Log Files

The Active Directory Synchronization module provides the following logs.

Time and Status Log

The time and status is logged in the following location:

AgilePointServer\log\[DateTime]-[server name].log

Example:

```
3/12/2012 12:53:29 PM>>
Synchronization started on 3/12/2012 12:53:27 PM

Path=LDAP://DC=MYDOMAIN,DC=com, UserLogonDomainName=MYDOMAIN
43 groups found.
   Synchronizing users
        Updating user 'MYDOMAIN\John.Sample'. User full name:John Sample,
   department:

Synchronization finished on 3/12/2012 12:53:29 PM.
```

Error Log

Errors are logged in the following location:

AgilePointServer\log\ADSynchModule.log

Example:

```
2012-03-12 12:53:27.732 >>> Active Directory group synchronizer
'ADSyncModule' has been started. Configuration: every Day at 1 O'clock,
register user automatically=True, Path=LDAP://DC=ASTN,DC=com,
Domain=ASTN
```

Notifications

In addition to log files that keep track of the synchronization statuses, the synchronization module also provides email notification capability. Email notification is sent out to the AgilePoint System User with information about the synchronization. This will allow the system user to determine if there is a need to manually synchronize the groups or users in the event of failed synchronization.

DBSyncModule Extension

The DBSyncModule AgileConnector extension allows you to synchronize custom user and group database tables with AgilePoint groups automatically.

Requirements

The following are requirements for the DBSyncModule AgileConnector:

- The AgilePoint System User (as defined in the AgilePoint Server Configuration utility) should be a Database user.
- AgilePoint Server's Application Pool's Identity user account (as configured in IIS) needs to have read
 permissions for the appropriate database.

Enabling the Extension

To enable the AgilePoint Server extension:

- Open the AgilePoint Server Configuration utility and go to the Extension window.
- Click the Ellipses button next to the Assembly field and add the following assembly:

...\AgilePointServer\bin\DBSyncModule.dll

- 3. Leave the Impersonator field blank.
- 4. Click **OK**. Now you will need to configure the module to schedule the synchronization.
- 5. Click the **Configure** button, and specify the desired configuration settings.

In the configuration interface, specify the following information:


- Connection Provide a valid database connection string.
- **Query** Provide the SQL query to fetch records from a table. The query must fetch the following fields, which are mandatory:
 - TITLE
 - USER_NAME
 - FULL_NAME
 - DEPARTMENT
 - EMAIL ADDRESS
 - MANAGER
 - GROUP_NAME

To check that the query was set up correctly, click Verify Query.

- Schedule Specify the synchronization with the frequency of every day, week, or month and at a
 particular time of day starting with the day you set the schedule.
- Option This section provides an option to select what action needs to be taken when a database
 member is not an AgilePoint user. Either one can select to register user to AgilePoint automatically or
 send a notification to AgilePoint System user.

Configuration for Database Groups/Users Synchronization Window

Specifies the configuration details for synchronizing AgilePoint Users and Groups with the user information resulting from a database query.



Prerequisites

Before configuring, you must `enable the DBSync Module Extension AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the **Extensions** tab, select **DBSyncModule**.
- 4. Click Configure.

Field Name	Definition
Connection String	Definition:
	Specifies the connection string to be used to connect to the database.
	Allowed Values:
	A valid connection string.
	Default Value:
	server=localhost;database=pubs;trusted_Connection=yes
	Custom Attributes:
	Yes
	Example:
	server=DataServer;database=StoreDb;trusted_Connectio
Query	Definition:
	The SQL query used to fetch the records from the database.
	Allowed Values:
	A valid SQL query.
	The query must fetch the following fields, which are mandatory:
	• TITLE
	• USER_NAME
	• FULL_NAME
	• DEPARTMENT
	EMAIL_ADDRESS
	• MANAGER
	GROUP_NAME

Field Name	Definition
VerifyQuery	Function: Verifies whether the specified query is valid.
Schedule	Function: The frequency for database synchronization. Synchronization can occur every day, week, or month, at a particular time or day.
If Active Directory group member is not AgilePoint user	 Definition: Specifies what actions to take if a member of your Active Directory is not a registered AgilePoint user. Allowed Values: Register user to AgilePoint automatically
Sync all Lync IDs with email IDs	Definition: Synchronizes all of your users' Lync IDs with their email IDs. This synchronization occurs each time and Active Directory synchronization occurs. AgilePoint recommends using this option only if all of your users' messaging IDs and email IDs are the same. Allowed Values: Selected - Synchronizes Lync IDs with users' email IDs. Deselected - Does not synchronize Lync IDs with users' email IDs. Default Value: Deselected
Sync all Yammer IDs with email IDs	Definition: Synchronizes Yammer IDs with AgilePoint users' email IDs. This synchronization occurs each time and Active Directory synchronization occurs.

Field Name	Definition
	AgilePoint recommends using this option only if all of your users' messaging IDs and email IDs are the same.
	Allowed Values:
	 Selected - Synchronizes Yammer IDs with users' email IDs.
	 Deselected - Does not synchronize Yammer IDs with users' email IDs.
	Default Value:
	Deselected

Group Member Synchronization Rules

- Only groups that have already been added into AgilePoint will be synchronized with the database. New
 groups will be added automatically to AgilePoint when the group name starts with a Group prefix value. The
 new groups will automatically be assigned to the default "Users" Role. If a group prefix value is empty, then
 new groups can be added manually through the Enterprise Manager interface.
- The changes of user members (adding or removing) in the database will be synchronized to AgilePoint but the changes in AgilePoint groups will NOT be synchronized back to the database.
- The synchronization only applies to member association (Add or Remove) within the groups.
- When a new member is added to the database, this member will also be added to the corresponding AgilePoint group. If the actual user entity is not registered in AgilePoint yet, the user entity will be registered to AgilePoint automatically.
- When a member is removed from the database, this member in the corresponding AgilePoint group will also be removed. The actual user entity will NOT be removed from AgilePoint as the same user entity can also be associated with other groups in the system.

User Synchronization Rules

Changes to the following database field properties will be synchronized to AgilePoint. Other properties will NOT be synchronized.

- Full Name
- Email Address
- Department
- Title
- Manager

Scheduling

The schedule of the synchronization is set through the module's configuration interface. The synchronization can be performed at a particular time of day with the frequency of every day, every week, or every month.

For example, if you schedule the synchronization to be performed at 2am on Jan. 1 and you also select **Every day** as the frequency, the synchronization will be started automatically at 2am on Jan 1, Jan 2, Jan 3, etc.

The following table summarizes the different ways that the schedule can be set for the synchronization.

Frequency	Time	1st Sync	2nd Sync	3rd Sync	4th Sync	5th Sync
Every Day	2am	Jan. 1	Jan. 2	Jan. 3	Jan. 4	Jan. 5
Every Week	2am	Jan. 1	Jan. 8	Jan. 15	Jan. 22	Jan. 29
Every Month	2am	Jan. 1	Feb. 1	March. 1	April. 1	May. 1

The synchronizations typically happen within five minutes of the scheduled time. For example, if the scheduled time is 2am, the actual synchronization could happen between 1:55am to 2:05am.



Note: The scheduling pattern (daily, weekly, or monthly) and scheduling time should be the same for multiple AgileConnectors of the same type.

Exception Handling

This module also provides exception handling for the scheduling. In the event that your server is down during the scheduled synchronization, as soon as your server is back online, the synchronization will be automatically kicked off. After that, the next synchronization will resume the original schedule.

Log Files



Note: The SharePoint Groups Synchronization module also writes log messages to the SPSyncModule.log file. The SPSyncModule.log file can also be found at the AgilePointServer\log folder. This log file contains detail information about each synchronization operation, such as the status of each group, or what users were unable to be registered to AgilePoint.

The following is an example of the log message in the ActiveDirectorySynchronizer.log file:

```
3/1/2005 5:51:49 PM>> Synchronization has started
to perform on 3/1/2005 5:51:47 PM
Synchronizing Users Registering user 'MYDOMAIN\Test1' to
AgilePoint. User full name: Test1, department: Testing
```

Notifications

In addition to log files that keep track of the synchronization statuses, the synchronization module also provides email notification capability. Email notification is sent out to the AgilePoint System User with information about the synchronization. This will allow the system user to determine if there is a need to manually synchronize the groups or users in the event of failed synchronization.

Email Approval Extension

Using email approval, process participants can approve documents or requests through email, without accessing their task lists. The MailApproval AgileConnector supports the following functionality:

Approve or reject tasks using a simple email reply

- Multiple AgileConnector configurations
- Network load balancing

Requirements

One of the following:

- A POP3 mailbox configured with a valid account in the AgilePoint Server Configuration
- An IMAP4 mailbox configured with a valid account in the AgilePoint Server Configuration
- An Exchange Server mailbox with a valid account

Enabling the Email Approval AgileConnector

To enable the Email Approval AgileConnector, do the following.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the Extensions tab, click Add.
- 2. In the **Impersonator** field, enter the AgilePoint user name that is used to connect to your email server. By default, this is the AgilePoint Service Account.
- Browse to the assembly [AgilePoint Server installation folder]\bin
 \Ascentn.AgileConnector.MailApproval.dll, and then click OK to add this extension to AgilePoint Server.

Configuring the Email Approval AgileConnector

To configure the Email Approval AgileConnector, do the following.

Prerequisites

- Before you register the Email Approval AgileConnector, you must register the Event Service AgileConnector.
- Before configuring, you must enable the Email Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the Configure Email Approval window, click the Settings tab.

Instructions

1. On the **Settings** tab, complete the following fields:

Field Name	Definition
POP3 Server	Definition: Specifies the host name or IP address of the POP3 server. To access this field, select POP3. Allowed Values: ■ A valid host name or IP address for your POP3 server. Default Value: None Example: Demo3
POP3 Port	Definition: Specifies the port number which is configured to communicate with your POP3 server. To access this field, select POP3. Allowed Values: A valid port number. Default Value: 110
SSL-Connection	Definition: Specifies whether the POP3 server uses an SSL encrypted connection. To access this field, select POP3 or IMAP. Allowed Values: An appSettings key in the following format: Selected - SSL communication is enabled. Deselected - SSL communication is disabled. Default Value: Deselected

Field Name	Definition
Microsoft Exchange Server URL	Definition: Specifies the Exchange Server URL. To access this field, select the Microsoft Exchange Server mode.
	Allowed Values:
	https://[host name]:[port]
	Default Value: None
	Custom Attributes:
	Yes
	Example:
	https://agilepoint.com:2030
IMAP4 Server	Definition:
	Specifies the host name or IP address of the IMAP4 Server.
	To access this field, select IMAP .
	Allowed Values:
	 A valid host name or IP address for your IMAP4 Server.
	Default Value:
	None
	Example:
	Demo3
IMAP4 Port	Definition:
	Specifies the port number that is configured for communication with your IMAP4 server.
	To access this field, select IMAP .
	Allowed Values:
	A valid port number.
	Default Value:
Exchange WebService URL	<u>Definition:</u>
l	Specifies the Exchange WebService URL.

Field Name	Definition
	To access this field, select EWS mode.
	Allowed Values:
	https://[ExchangeServerMachineName]:[Port]/ EWS/exchange.asmx
	Default Value:
	None
	Custom Attributes:
	Yes
	Example:
	https://agilepoint.com:2030/EWS/Exchange.asmx
Login	Definition:
	Specifies the username for the mailbox containing the email-based approvals.
	Allowed Values:
	A valid username.
	Default Value:
	None
Password	Definition:
	The password for the authentication account.
	Allowed Values:
	A valid password.
	Default Value:
	None
	Custom Attributes:
	Yes
Schedule every	Definition:
	Specifies the time interval in minutes for the AgileConnector to check the mailbox for new incoming email.
	Allowed Values:
	Any integer.
	Default Value:

Field Name	Definition
	1
Delete incorrect approval emails	Definition: Deletes all the emails from the mailbox once it is read from the server. Allowed Values: Selected - Deletes the emails from the mailbox. Deselected - Does not delete the emails from the mailbox. Default Value: Deselected
Basic	Definition: Saves the basic information about the Email Approval AgileConnector in the AgilePoint Server log file. Allowed Values: Selected - Saves the basic information in the AgilePoint Server log file. Deselected - Does not save the basic information in the AgilePoint Server log file. Default Value: Selected
Debug	Definition: Saves the debug information about the email approval AgileConnector in the AgilePoint Server log file. Allowed Values: Selected - Saves the debugging information in the AgilePoint Server log file. Deselected - Does not save the debugging information in the AgilePoint Server log file. Default Value: Deselected
Test	Function:

Field Name	Definition
	Verifies whether the specified account credential is valid.

Configuring Automatic Replies for Email Approval Success or Failure

You can set up the Email Approval AgileConnector so that it will send a custom automated reply message when an email approval succeeds or fails.

To set up automated approvals, do the following.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the **Configure Email Approval** window, click the **Acknowledgement** tab.

Instructions

1. On the Acknowledgement tab, complete the following fields as required for your environment.

Field Name	Definition
Failed email approval reply message	Definition: Specifies the content the automated message sent to participants when an email approval fails. Allowed Values: A text string that represents the body of the email. Default Value: A default email message body.
Successful email approval reply message	Definition: Specifies the content the automated message sent to participants when an email approval is successful. Replies for successful approvals are optional. Allowed Values: A text string that represents the body of the email. To enable email replies for successful approvals, the check box must be selected. Default Value:

Field Name	Definition
	Deselected, with no default message.

Configuring SharePoint Connectivity for the Email Approval AgileConnector

To set up the Email Approval AgileConnector so that it can update values in SharePoint ListForm or InfoPath processes, do the following.

Prerequisites

 If you are using Forms Based Authentication, set this up in your SharePoint environment using the instructions from Microsoft: http://msdn.microsoft.com/en-us/library/bb975136%28v=office.12%29.aspx

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the **Configure Email Approval** window, click the **Connect to SharePoint** tab.

Instructions

1. On the Connect to SharePoint tab, complete the following fields as required for your environment.

Field Name	Definition
Windows Authentication	Definition: Specifies whether, and what type, of Windows Authentication is used to connect to SharePoint.
Claims Authentication	Definition: Specifies whether to use Claims authentication, and what type of Claims authentication, to use to connect to SharePoint. Allowed Values: If this option is selected, the following types of Claims Authentication are available: Form Based Authentication - Activates Forms based authentication using a custom membership provider to connect to an onpremises SharePoint environment. Office 365 - Activates Claims authentication to connect to SharePoint in an Office 365

Field Name	Definition
	environment. This option can be used side-by- side with on-premises SharePoint. • Federated Authentication - Activates Federated authentication to connect to SharePoint for example, ADFS. • Note: Out of the box, AgilePoint supports ADFS authentication. If you
	want to use your own authentication provider, see Federated Authentication Example in the Documentation Library. Default Value:
	Deselected
Domain	Definition: The authentication domain. This does not apply to Forms-Based Authentication.
Username	The user ID of the SharePoint authentication account.
Password	Definition: The password for the authentication account.
	Allowed Values: A valid password.
	Default Value: None
	Custom Attributes: Yes
Fed Auth Url	Definition: The URI of the federated authentication provider. This provider issues security tokens for federated authentication. Allowed Values: A valid federated authentication provider URI. Default Value: None Custom Attributes: No Example:

Field Name	Definition
	https://fs.agilityclouds.com

Logging

The MailApproval module writes log messages to the AgilePoint Server log file which can be found at AgilePointServer\Log. The following is an example of a log message in the file:

```
8/12/2008 8:04:05 >>> AgileConnector MailApproval Started.

Pop3 server, Server=110, Port=in.telenet.be, userName=xxxxxx 8/12/2008
8:05:08 >>> TaskId: 65B82D87B3F34765B2DDE64791786961 8/12/2008
8:05:08 >>> {Approval [X] = {/pd:myFields/pd:Approved}=True}
8/12/2008 8:05:08 >>> {Remarks [This is a test] = {/pd:myFields/pd:Remark}} 8/12/2008 8:05:08 >>> Number of email based workitems received: 11
```

POP3 Limitations

The following limitations apply when using Email Approval on a POP3 server:


- There is no response while testing a connection if you deselect SSL-Connect when the POP3 Server requires SSL.
- The incorrect emails will not be deleted from the mailbox even if the option Delete incorrect approval
 emails is selected.

Creating an Email Template to Support Approvals

For information about creating an email template for direct approvals, see the Envision Online Help.

Email Approval Configuration Window - Settings Tab

Specifies the basic settings for the Email Approval AgileConnector.



Prerequisites

- Before you register the Email Approval AgileConnector, you must register the Event Service AgileConnector.
- Before configuring, you must enable the Email Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the Configure Email Approval window, click the Settings tab.

Field Name	Definition
POP3 Server	 Definition: Specifies the host name or IP address of the POP3 server. To access this field, select POP3. Allowed Values: A valid host name or IP address for your POP3 server. Default Value: None Example: Demo3
POP3 Port	Definition: Specifies the port number which is configured to communicate with your POP3 server. To access this field, select POP3. Allowed Values: A valid port number. Default Value: 110
SSL-Connection	Definition: Specifies whether the POP3 server uses an SSL encrypted connection. To access this field, select POP3 or IMAP. Allowed Values: An appSettings key in the following format: Selected - SSL communication is enabled. Deselected - SSL communication is disabled. Default Value: Deselected
Microsoft Exchange Server URL	Definition: Specifies the Exchange Server URL.


Field Name	Definition
	To access this field, select the Microsoft Exchange Server mode.
	Allowed Values:
	https://[host name]:[port]
	Default Value:
	None
	Custom Attributes:
	Yes
	Example:
	https://agilepoint.com:2030
IMAP4 Server	Definition:
	Specifies the host name or IP address of the IMAP4 Server.
	To access this field, select IMAP .
	Allowed Values:
	 A valid host name or IP address for your IMAP4 Server.
	Default Value:
	None
	Example:
	Demo3
IMAP4 Port	Definition:
	Specifies the port number that is configured for communication with your IMAP4 server.
	To access this field, select IMAP .
	Allowed Values:
	A valid port number.
	Default Value:
	110
Exchange WebService URL	Definition:
	Specifies the Exchange WebService URL.
	To access this field, select EWS mode.
	Allowed Values:

Field Name	Definition
	https://[ExchangeServerMachineName]:[Port]/EWS/exchange.asmx
	Default Value:
	None
	Custom Attributes:
	Yes
	Example:
	https://agilepoint.com:2030/EWS/Exchange.asmx
Login	Definition:
	Specifies the username for the mailbox containing the email-based approvals.
	Allowed Values:
	A valid username.
	Default Value:
	None
Password	Definition:
	The password for the authentication account.
	Allowed Values:
	A valid password.
	Default Value:
	None
	Custom Attributes:
	Yes
Schedule every	Definition:
	Specifies the time interval in minutes for the AgileConnector to check the mailbox for new incoming email.
	Allowed Values:
	Any integer.
	Default Value:
	1
Delete incorrect approval emails	Definition:

Field Name	Definition
	Deletes all the emails from the mailbox once it is read from the server.
	Allowed Values:
	Selected - Deletes the emails from the mailbox.
	 Deselected - Does not delete the emails from the mailbox.
	Default Value:
	Deselected
Basic	Definition:
	Saves the basic information about the Email Approval AgileConnector in the AgilePoint Server log file.
	Allowed Values:
	 Selected - Saves the basic information in the AgilePoint Server log file.
	 Deselected - Does not save the basic information in the AgilePoint Server log file.
	Default Value:
	Selected
Debug	Definition:
	Saves the debug information about the email approval AgileConnector in the AgilePoint Server log file.
	Allowed Values:
	 Selected - Saves the debugging information in the AgilePoint Server log file.
	 Deselected - Does not save the debugging information in the AgilePoint Server log file.
	Default Value:
	Deselected
Test	Function:
	Verifies whether the specified account credential is valid.

Email Approval Configuration Window - Acknowledgement Tab

Specifies the configuration of Email Approval AgileConnector for sending a custom automated reply message when an email approval succeeds or fails.



Prerequisites

- Before you register the Email Approval AgileConnector, you must register the Event Service AgileConnector.
- Before configuring, you must enable the Email Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.


- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the **Configure Email Approval** window, click the **Acknowledgement** tab.

Field Definitions

Field Name	Definition
Failed email approval reply message	Definition: Specifies the content the automated message sent to participants when an email approval fails. Allowed Values: A text string that represents the body of the email. Default Value: A default email message body.
Successful email approval reply message	Definition: Specifies the content the automated message sent to participants when an email approval is successful. Replies for successful approvals are optional. Allowed Values: A text string that represents the body of the email. To enable email replies for successful approvals, the check box must be selected. Default Value: Deselected, with no default message.

Email Approval Configuration Window - Connect to SharePoint Tab

Specifies the configuration of Email Approval AgileConnector for updating values in SharePoint ListForm or InfoPath processes.



Prerequisites

- Before you register the Email Approval AgileConnector, you must register the Event Service AgileConnector.
- Before configuring, you must enable the Email Approval AgileConnector.
- If you are using Forms Based Authentication, set this up in your SharePoint environment using the instructions from Microsoft: http://msdn.microsoft.com/en-us/library/bb975136%28v=office.12%29.aspx

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select MailApproval.
- 4. Click Configure.
- 5. On the Configure Email Approval window, click the Connect to SharePoint tab.

Field Name	Definition
Windows Authentication	Definition: Specifies whether, and what type, of Windows Authentication is used to connect to SharePoint.
Claims Authentication	Definition: Specifies whether to use Claims authentication, and what type of Claims authentication, to use to connect to SharePoint. Allowed Values: If this option is selected, the following types of Claims Authentication are available: Form Based Authentication - Activates Forms based authentication using a custom membership provider to connect to an onpremises SharePoint environment. Office 365 - Activates Claims authentication to connect to SharePoint in an Office 365 environment. This option can be used side-byside with on-premises SharePoint. Federated Authentication - Activates Federated authentication to connect to SharePoint for example, ADFS. Note: Out of the box, AgilePoint supports ADFS authentication. If you want to use your own authentication provider, see Federated Authentication Example in the Documentation Library. Default Value: Deselected
Domain	Definition: The authentication domain. This does not apply to Forms-Based Authentication.
Username	Definition: The user ID of the SharePoint authentication account. Allowed Values: A valid user name.

Field Name	Definition
	Default Value:
	None
	Custom Attributes:
	No
Password	Definition:
	The password for the authentication account.
	Allowed Values:
	A valid password.
	Default Value:
	None
	Custom Attributes:
	Yes
Fed Auth Url	Definition:
	The URI of the federated authentication provider. This provider issues security tokens for federated authentication.
	Allowed Values:
	A valid federated authentication provider URI.
	Default Value:
	None
	Custom Attributes:
	No
	Example:
	https://fs.agilityclouds.com

Enterprise Social AgileConnector

The Enterprise Social AgileConnector facilitates communication with Yammer applications.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.

Enabling the Enterprise Social AgileConnector

To enable the Enterprise Social AgileConnector, do the following.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the Extensions tab, click Add.
- 2. In the **Impersonator** field, enter the AgilePoint user name that is used to connect to your email server. By default, this is the AgilePoint Service Account.
- 3. Browse to the assembly [AgilePoint Server installation folder]\bin \AgilePoint.AgileConnector.EnterpriseSocial.dll.
- 4. Click OK.

Configuring the Enterprise Social AgileConnector

To configure the Enterprise Social AgileConnector, do the following.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Enterprise Social Network AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select EnterpriseSocial.
- 4. Click Configure.

Instructions


1. On the Social Network Configuration Dialog window, complete the following fields as required.

Field Name	Definition
Application Filter	Definition: Filters the process template based on the application name. The messaging service is enabled on the process templates identified in this field. Allowed Values: One or more valid application names. Multiple application names must be separated with a semicolon (;). Default Value: None
Send task assignment notification	Definition: Specifies that the Enterprise Social Network AgileConnector sends an notification to the participants about the task assignment. Allowed Values: Selected - Sends an notification to the participants. Deselected - No notification is sent. Default Value: Selected
Retry Delay In Retries	Definition: Specifies the number of times you want to retry an operation that failed due to a "Too Many Requests" exception. Allowed Values: Any integer. Default Value: 5
	Definition: Specifies the number of seconds you want to delay between retries after an operation fails due to a "Too Many Requests" exception. Allowed Values:

Field Name	Definition
	Any integer.
	Default Value:
	30
Thread Pool	Definition: Specifies the maximum number of concurrent connections between the AgilePoint Server and Yammer. Allowed Values: Any integer. Default Value: 1
Trace Mode	Definition: Specifies whether the AgileConnector writes the detail logging information into the log file. Allowed Values: Selected - Indicates that the AgileConnector writes the detail logging information into the log file. Deselected - Indicates that the AgileConnector does not write the detail logging information into the log file.
	Default Value: Selected

Social Network Configuration Dialog

Specifies the configuration details for the Enterprise Social AgileConnector.



Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Enterprise Social Network AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select EnterpriseSocial.
- 4. Click Configure.

Field Name	Definition
Application Filter	Definition:
	Filters the process template based on the application name.
	The messaging service is enabled on the process templates identified in this field.
	Allowed Values:
	One or more valid application names.

Field Name	Definition
	Multiple application names must be separated with a semicolon (;).
	Default Value:
	None
Send task assignment notification	Definition: Specifies that the Enterprise Social Network
	AgileConnector sends an notification to the participants about the task assignment.
	Allowed Values:
	 Selected - Sends an notification to the participants.
	Deselected - No notification is sent.
	Default Value:
	Selected
Retry	Definition:
	Specifies the number of times you want to retry an operation that failed due to a "Too Many Requests" exception.
	Allowed Values:
	Any integer.
	Default Value:
	5
Delay In Retries	Definition:
	Specifies the number of seconds you want to delay between retries after an operation fails due to a "Too Many Requests" exception.
	Allowed Values:
	Any integer.
	Default Value:
	30
Thread Pool	Definition:
	Specifies the maximum number of concurrent connections between the AgilePoint Server and Yammer.
	Allowed Values:

Field Name	Definition
	Any integer.
	Default Value:
	1
Trace Mode	Definition: Specifies whether the AgileConnector writes the detail logging information into the log file. Allowed Values: Selected - Indicates that the AgileConnector writes the detail logging information into the log file. Deselected - Indicates that the AgileConnector does not write the detail logging information into the log file. Default Value: Selected

ContentListener AgileConnector

The Content Listener AgileConnector extension enables you to initiate processes on items in a SharePoint list or library based on conditions you specify. The Content Listener AgileConnector runs a CAML query based on a schedule you specify to evaluate the items in the SharePoint list and initiate the appropriate processes.

For example, you could initiate an escalation processes for all items in a SharePoint list that are designated high priority or past due.

Enabling the ContentListener AgileConnector

To enable the AgilePoint Server extension:

- 1. Open the AgilePoint Server Configuration utility and go to the Extension window.
- 2. Click the Add button.
- 3. Click the **Ellipses** button on the Extension window and add the following assembly:

...\AgilePointServer\bin\Ascentn.AgileConnector.ContentListener.dll



Note: The **Name** field will be auto-populated, DO NOT change it. Leave the **Impersonator** field blank.

Configuring the ContentListener AgileConnector

Once you have added the ContentListener AgileConnector

Prerequisites

Enable the ContentListener AgileConnector.
 For more information, see Enabling the ContentListener AgileConnector in the Documentation Library.

Navigation

1. On the **AgilePoint Server Configuration Utility**, click the **Extension** Tab.

Instructions

- 1. On the Extension tab, select ContentListener.
- 2. Click Configure.
- 3. On the **SharePoint Content Listener Connector Configuration** window, complete the fields as described in this topic.

Field Name	Definition
Add Task	Creates a new task.
Delete Task	Removes an existing task.
SharePoint Access Credentials	The credentials you wan to use to authenticate to SharePoint.
	AgilePoint System Account - The standard AgilePoint system account
	Custom Account - Credentials for an account you specify in the Domain, User, and Password fields.
Schedule Name	A free text name for the schedule.
Site	The URL of the SharePoint site associated with the process.
List	The SharePoint list associated with the process.
Process	The process model to use for the initiated process.
CAML Query	Specifies the CAML query used to initiate the process.
	You can type or paste a CAML query in the box, or click the Ellipses button to open the CAML Query Configuration window.
	For more information, see CAML Query Builder Configuration Window - List and View Fields Tab.

Field Name	Definition
Recurrence	Specifies the schedule to run the CAML query. Options are:
	One Time - The schedule occurs only one time.
	By Minute - The schedule occurs once every specified number of minutes.
	By Day - Recurs at the specified time on the specified interval of days.
	By Week - Recurs at the specified time on the specified days.
	By Month - Recurs at the specified time on the specified days of the specified months.

DataService AgileConnector

This AgilePoint Server extension (AgileConnector) allows you to enable application data services to collect and track application data. The Data Services includes two core components:

- Data Population
- Data Tracking

Data Population allows you to write to a database the desired application data values. The data can then be used for reporting purposes. The configuration is done via AgilePoint Envision. For more information, see Data Services in the Documentation Library.

Data Tracking provides the functionality to set up fields in AgilePoint Envision to be monitored for changes to application data, for example you can see for a specific field on a form, the "Old Value" and if the data changes, the "New Value". This viewpoint is provided via the AgilePoint Enterprise Manager Data Tracking tab.

Enabling the DataService AgileConnector

To enable the DataService AgileConnector, do the following.

Good to Know

• To support multiple applications, you can configure multiple AgileConnectors, or list multiple applications within the Application Filter of one AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the Extensions tab, click Add.
- Click the Ellipses button next to the Assembly field to browse the assembly [AgilePoint Server installation folder] \bin\Ascentn.AgileConnector.DataService.dll.

Note the following:

- The **Name** field appears with the default AgileConnector name. Do not change this value.
- The **Impersonator** field must be blank.
- 3. Click Configure.
- 4. On the **Data Service Configuration** window, complete the following fields as required.

Field Name	Definition
Application Filter	Definition: Filters the process template based on the process model type or name.
	Allowed Values:
	 SPSIntegration - Uses only process models created using InfoPath, SPList and SPDoc process templates.
	 AgileForms - Uses only process models created using AgileForms process templates.
	 MyApplication - Uses only process models created using Generic process templates — usually ASP.NET applications.
	 Custom application name - Uses only process models with a custom application name specified in the process template.
	Multiple application names must be separated with a semicolon (;).
	Default Value:
	MyApplication
Connection String	Definition:
	Specifies the connection string to be used to connect to the Data Tracking database.
	Allowed Values:
	A valid connection string.
	Default Value:
	Data Source=.;Integrated Security=SSPI;Initial Catalog=AgilePointTracking
	Example:
	Data Source=mydomain;Integrated Security=SSPI;Initial Catalog=AgilePointTracking

EventService AgileConnector

This AgilePoint Server extension (AgileConnector) allows you to initiate processes automatically via scheduling, email, database, or file dropping.

Enabling the EventService AgileConnector

To enable the AgilePoint Server extension:

- 1. Open the AgilePoint Server Configuration utility and go to the Extension window.
- 2. On the Extension window, click Add.
- 3. Click the Ellipses button on the Extension window and add the following assembly:

```
...\AgilePointServer\bin\Ascentn.AgileConnector.EventService.dll
```



Note: The **Name** field will be auto-populated, DO NOT change it. Leave the **Impersonator** field blank.

After registering the EventService AgileConnector, you can check the AgilePoint Server log file for verification. If you see the two lines as shown below in the log file, this means that the EventService AgileConnector configuration is correct.

Lync Approval AgileConnector

The Lync Approval AgileConnector enables you to receive messages via Lync that can affect your process data. A common use for this functionality is approvals.

AgilePoint Server installed in Windows Service mode.

Enabling the Lync Approval AgileConnector

To enable the Lync Approval AgileConnector, do the following.

Prerequisites

AgilePoint Server installed in Windows Service mode.

Navigation

- On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- On the Extensions tab, click Add.
- 2. In the Impersonator field, enter the AgilePoint user name that is used to connect to your email server.

- By default, this is the AgilePoint Service Account.
- 3. Browse to the assembly [AgilePoint Server installation folder]\bin \AgilePoint.LyncApproval.AgileConnector.dll.
- 4. Click OK.

Configuring the Lync Approval AgileConnector

To configure the Lync Approval AgileConnector, do the following.

Prerequisites

- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Lync Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select LyncApproval.
- 4. Click Configure.

Instructions


1. On the Configure Lync Approval AgileConnector window, complete the following fields as required.

Field Name	Definition
Application Filter	Definition: Filters the process template based on the application name. The messaging service is enabled on the process templates identified in this field. Allowed Values: One or more valid application names. Multiple application names must be separated with a semicolon (;). Default Value: None
Lync Sign-In Address	Definition: Specifies the email address for the Lync account. Allowed Values: A valid email address.

Field Name	Definition
	Default Value:
	None
Lync Sign-In Domain	Definition: Specifies the domain name for the Lync account used by AgilePoint Server. Allowed Values: A valid domain name. Default Value: None
Password	Definition: The password for the authentication account. Allowed Values: A valid password. Default Value: None
Send Task Assignment Notifications to Lync	Definition: Specifies that the Lync Approval AgileConnector sends the task assignment notification to the participants via Lync. Allowed Values: Selected - Sends a task assignment notification via Lync. Deselected - No task assignment notification is sent. Default Value: Deselected

Lync Approval AgileConnector Configuration Window

Specifies the configuration options for the Lync Approval AgileConnector.




Prerequisites

- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Lync Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select LyncApproval.
- 4. Click Configure.



Field Name	Definition
	None
Lync Sign-In Address	Definition: Specifies the email address for the Lync account. Allowed Values: A valid email address. Default Value: None
Lync Sign-In Domain	Definition: Specifies the domain name for the Lync account used by AgilePoint Server. Allowed Values: A valid domain name. Default Value: None
Password	Definition: The password for the authentication account. Allowed Values: A valid password. Default Value: None
Send Task Assignment Notifications to Lync	Definition: Specifies that the Lync Approval AgileConnector sends the task assignment notification to the participants via Lync. Allowed Values: Selected - Sends a task assignment notification via Lync. Deselected - No task assignment notification is sent. Default Value: Deselected

MSMQ AgileConnector

This AgilePoint Server extension (AgileConnector) allows you to run Microsoft Message Queuing.

Enabling the MSMQ AgileConnector

To enable the AgilePoint Server extension:

- Open the AgilePoint Server Configuration utility and go to the Extension window.
- 2. Click the Add button.
- 3. Click the Ellipses button on the Extension window and add the following assembly:

...\AgilePointServer\bin\Ascentn.AgileConnector.MSMQ.dll



Note: The **Name** field will be auto-populated, DO NOT change it. Leave the **Impersonator** field blank.

- 4. Click OK.
- 5. Click the **Configure** button and specify the desired configuration settings.

MSWFRuntime AgileConnector

This AgilePoint Server extension (AgileConnector) allows you to enable AgilePoint Server to host and execute Microsoft Windows Workflow Foundation activities at run time. AgilePoint provides the Sequential Workflow AgilePart that can be initiated from an AgilePoint process as a sub-process to facilitate the data-exchange between AgilePoint and Windows Workflow Foundation. The Sequential Workflow AgilePart can be customized by leveraging this AgileConnector for Windows Workflow Foundation.



Note: This AgileConnector requires the .NET Framework 3.0 or later.

This AgileConnector is implemented as a class named **Ascentn.AgileConnector.MSWFRuntime** in the **Ascentn.AgileConnector.MSWFRuntime** assembly. The assembly is located by default in the ... **\AgilePointServer\bin** folder under your AgilePoint Server installation location.

Once you have enabled and configured the AgileConnector from the AgilePoint Server Configuration utility's Extensions window (as shown below), then you can create AgilePoint workflow applications that execute Windows Workflow Foundation activities and workflow applications.

Enabling the MSWFRuntime AgileConnector

To enable the AgilePoint Server extension:

- 1. Open the AgilePoint Server Configuration utility and go to the **Extension** window.
- 2. Click the Add button.
- 3. Ensure the database is configured properly.
- 4. Click the Ellipses button on the Extension window and add the following assembly:

...\AgilePointServer\bin\Ascentn.AgileConnector.MSWFRuntime.dll



Note: The **Name** field will be auto-populated, DO NOT change it. Leave the **Impersonator** field blank.

- 5. Click OK.
- 6. Click the **Configure** button and specify the desired configuration settings. It prompts the following window for the Windows Workflow Foundation persistence and tracking database configuration.

This step requires DBA privileges for creating tables and stored procedures. Also, the following SQL files are used:

- SqlPersistenceService Logic.sql
- SqlPersistenceService_Schema.sql
- Tracking_Logic.sql
- Tracking_Schema.sql

These files can be found in the AgilePoint Server folder at ...\AgilePoint Server\Components\Workflow Foundation.

The Database Server needs to be same as AgilePoint Server, but the Database can be different.

7. Once finished with the configuration, click **OK**.

RemotingService AgileConnector

This AgilePoint Server extension (AgileConnector) allows you to enable and configure AgilePoint Server to use Remoting to interact with AgilePoint Server. This extension opens up a port that can be used to connect (via Remoting) to the AgilePoint Server Process Engine and API. This AgileConnector is implemented as a class named **Ascentn.Workflow.Extension.RemotingService** in the **Ascentn.AgileConnector.RemotingService.dll** assembly. The assembly is located by default in the ... **\AgilePointServer\bin** folder under your AgilePoint Server installation location.

Once you have enabled and configured the AgileConnector from the AgilePoint Server Configuration utility's Extensions window (as shown below), then you can create client applications that use Remoting to interact with AgilePoint Server.

Enabling the RemotingService AgileConnector

To enable the AgilePoint Server extension:

- Open the AgilePoint Server Configuration utility and go to the Extension window.
- 2. Click the Add button.
- Click the Ellipses button on the Extension window and add the following assembly:

...\AgilePointServer\bin\Ascentn.AgileConnector.RemotingService.dll



Note: The **Name** field will be auto-populated, DO NOT change it. Leave the **Impersonator** field blank.

- 4. Click OK.
- 5. Click the **Configure** button and specify the desired configuration settings.
- 6. Click OK.

SAP Integration AgileConnector

This AgilePoint Server extension (AgileConnector) enables you to run the SAP Integration component of the AgilePoint BPMS Suite.

Enabling the SAP AgileConnector

To configure the SAP AgileConnector, do the following.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the Extensions tab, click Add.
- Browse to the assembly [AgilePoint Server installation folder]\bin
 \Ascentn.AgileConnector.SAPIntegration.dll, and then click OK to add this extension to AgilePoint
 Server.

Configuring the SAP AgileConnector

To configure the SAP AgileConnector, do the following.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the **Extensions** tab, select the **SAPIntegration** AgileConnector.
- 2. Click the Configure button.
- 3. In the configuration window for the SAP Integration AgileConnector, configure the following fields as required.

Field Name	Definition
Max Threads for SAP Integration	Definition: Specifies the maximum number of concurrent connections between AgilePoint Server and SAP.
	Allowed Values: Any integer. Default Value:

Field Name	Definition
	5
Send Notification for Suspended Processes	Definition: Specifies whether the SAP Integration AgileConnector sends a notification to the AgilePoint system administrator if a process instances is suspended as a result of an SAP integration error. Allowed Values: Deselected - No email notification is sent. Selected - Sends an email notification if a process instance is suspended. Default Value: Deselected

Configuring the AgilePoint SharePoint Integration AgileConnector

This AgilePoint Server extension (AgileConnector) allows for the communication between AgilePoint Server and SharePoint. This extension is only applicable for the AgilePoint SharePoint Integration v2.

Prerequisites

- AgilePoint Server is installed.
- The credentials for the SharePoint Impersonator account.

The SharePoint Impersonator account is determined during pre-installation. For more information, see Creating a SharePoint Impersonator User Account in the Documentation Library.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the **Extension** tab, click on **Add**.
- Browse one of the following locations to open the file Ascentn.SharePoint.AgileConnector.dll:
 - For IIS installations, this file is located in the **bin** folder under the AgilePoint Server installation folder.
 - For Windows Service installations, this file is located in the **bin** folder under the path provided in the **Location** field in Windows Server Manager for the Windows Service instance you want to configure.
- 3. Change the **Name** from **AgileConnector** to **SPSIntegration**.
- 4. Enter the Impersonator (e.g. Administrator).

- 5. Click OK.
- 6. Optionally, you can click **Configure** to set the maximum thread for SharePoint access and to set the credential for SharePoint access. By default it will use the AgilePoint System User Account credential.
- When you have finished the configuration, on the AgilePoint Configuration window, click OK.
 Accept any informational messages.
 - If you are prompted to restart IIS or the AgilePoint Service, click Yes.

Configuring the SharePoint Integration AgileConnector

To configure the SPSIntegration extension, do the following.

Prerequisites

• If you are using Forms Based Authentication, set this up in your SharePoint environment using the instructions from Microsoft: http://msdn.microsoft.com/en-us/library/bb975136%28v=office.12%29.aspx

Navigation

- On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the **Extensions** tab, select **SPSIntegration**.
- 4. Click Configure.

Instructions

 On the AgileConnector for SharePoint window, configure the following fields as required for your environment, and then click OK.

Field Name	Definition
Max Threads for SharePoint Access	Definition: Specifies the maximum number of concurrent connections between AgilePoint Server and SharePoint. Allowed Values: Any integer. Default Value: 10
Windows Authentication	Definition: Specifies whether, and what type, of Windows Authentication is used to connect to SharePoint.
Claims Authentication	Definition:

Field Name	Definition
	Specifies whether to use Claims authentication, and what type of Claims authentication, to use to connect to SharePoint.
	Allowed Values:
	If this option is selected, the following types of Claims Authentication are available:
	 Form Based Authentication - Activates Forms based authentication using a custom membership provider to connect to an on-premises SharePoint environment.
	 Office 365 - Activates Claims authentication to connect to SharePoint in an Office 365 environment. This option can be used side-by- side with on-premises SharePoint.
	 Federated Authentication - Activates Federated authentication to connect to SharePoint for example, ADFS.
	Note: Out of the box, AgilePoint supports ADFS authentication. If you want to use your own authentication provider, see Federated Authentication Example in the Documentation Library.
	Default Value:
	Deselected
Domain	Definition:
	The authentication domain.
	This does not apply to Forms-Based Authentication.
Username	The user ID of the SharePoint authentication account.
Password	Definition: The password for the authentication account. Allowed Values: A valid password. Default Value:
	None
	Custom Attributes:
	Yes
Fed Auth Url	Definition:

Field Name	Definition
	The URI of the federated authentication provider. This provider issues security tokens for federated authentication.
	Allowed Values:
	A valid federated authentication provider URI.
	Default Value:
	None
	Custom Attributes:
	No
	Example:
	https://fs.agilityclouds.com
Use UTF8 Encoding	Definition:
	Specifies whether to use UTF-8 encoding when communicating with the external system.
	Allowed Values:
	Selected - Specifies to use UTF-8 encoding.
	 Deselected - Specifies not to use UTF-8 encoding.
	Default Value:
	Deselected
Send Notification for Suspended Processes	Definition:
	Specifies whether the SPSIntegration AgileConnector sends a notification to the AgilePoint system administrator if a process instances is suspended as a result of a SharePoint Integration error.
	Allowed Values:
	Deselected - No email notification is sent.
	 Selected - Sends an email notification if a process instance is suspended.
	Default Value:
	Deselected

SMS Service and Approval AgileConnector

The SMS AgileConnector enables you to send messages from a process via SMS. Optionally, you can use a third-party SMS listening service in order to receive SMS messages for responses such as approvals.

- AgilePoint Server installed in Windows Service mode.
- If you want to use Strikelron SMS listener functionality, you must set up an account with Strikelron. This is a
 paid account.
 - To register an account, visit www.strikeiron.com.
- If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.

Enabling the SMS Service and Approval AgileConnector

To enable the SMS Service and Approval AgileConnector, do the following.

Prerequisites

- AgilePoint Server installed in Windows Service mode.
- If you want to use Strikelron SMS listener functionality, you must set up an account with Strikelron. This is a
 paid account.
 - To register an account, visit www.strikeiron.com.
- If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- On the Extensions tab, click Add.
- In the Impersonator field, enter the AgilePoint user name that is used to connect to your email server.
 By default, this is the AgilePoint Service Account.
- 3. Browse to the assembly [AgilePoint Server installation folder]\bin \AgilePoint.AgileConnector.SMSService.dll.
- 4. Click OK.

Configuring the SMS Service and Approval AgileConnector

The Configuring the SMS Service and Approval AgileConnector supports two types of actions using SMS:

• Sending notifications based on events - SMS notifications are set up in the AgileWorks within a process model. Sending SMS notifications does not require a listener service account.

• **Listening for incoming responses for process input** - This is typically used for simple responses such as approve/reject. This requires a listener service account.

To configure the SMS Service and Approval AgileConnector, do the following.

Prerequisites

- AgilePoint Server installed in Windows Service mode.
- If you want to use Strikelron SMS listener functionality, you must set up an account with Strikelron. This is a
 paid account.
 - To register an account, visit www.strikeiron.com.
- If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.
- Before configuring, you must enable the SMS Service and Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select SMSService.
- 4. Click Configure.

Instructions

1. If you want to filter out process models that will not use SMS messaging, complete the following field.

Field Name	Definition
Application Filter	Definition:
	Filters the process template based on the application name.
	The messaging service is enabled on the process templates identified in this field.
	Allowed Values:
	One or more valid application names.
	Multiple application names must be separated with a semicolon (;).
	Default Value:
	None

2. To set the "from" name participants see in their SMS notifications, complete the following field:

Field Name	Definition
From Name in SMS Text	Definition:

Field Name	Definition
	Specifies the name displayed in an SMS text message.
	Allowed Values: A single line of text.
	Default Value: None.

- 3. If you want users to receive notifications when tasks are assigned, select **Send Notification to Users about Task Assignment**.
- 4. If you want AgilePoint to listen to incoming SMS messages to support SMS responses, do the following:
 - a. On the **Configure SMS Service AgileConnector** window, enter the user name and password for your SMS.


Field Name	Definition
User ID	Definition: Specifies the user name of the Strikelron service account. Allowed Values: A valid user name. Default Value: None Custom Attributes: No
Password	Definition: The password for the authentication account. Allowed Values: A valid password. Default Value: None
Schedule Interval	Definition: Specifies the number of minutes for the AgileConnector to wait before checking whether the task has been approved. Allowed Values: Any integer.

Field Name	Definition
	Default Value:
	1
SMS Service Provider	Definition:
	Specifies the name of the service provider.
	Allowed Values:
	A valid service provider name that appears in the list.
	If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.
	Default Value:
	Strikelron.

b. To test whether the SMS listener account is valid, click Test.

SMS Service and Approval AgileConnector Configuration Window

Specifies the configuration details of the SMS Service and Approval AgileConnector.



Prerequisites

- AgilePoint Server installed in Windows Service mode.
- If you want to use StrikeIron SMS listener functionality, you must set up an account with StrikeIron. This is a
 paid account.
 - To register an account, visit www.strikeiron.com.
- If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.
- Before configuring, you must enable the SMS Service and Approval AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select SMSService.
- 4. Click Configure.

Field Name	Definition
Application Filter	Definition: Filters the process template based on the application name. The messaging service is enabled on the process templates identified in this field. Allowed Values: One or more valid application names. Multiple application names must be separated with a semicolon (;). Default Value: None
User ID	Definition: Specifies the user name of the Strikelron service account. Allowed Values: A valid user name. Default Value: None

Field Name	Definition
	Custom Attributes:
	No
Password	Definition:
	The password for the authentication account.
	Allowed Values:
	A valid password.
	Default Value:
	None
From Name in SMS Text	Definition:
	Specifies the name displayed in an SMS text message.
	Allowed Values:
	A single line of text.
	Default Value:
	None.
Schedule Interval	Definition:
	Specifies the number of minutes for the AgileConnector to wait before checking whether the task has been approved.
	Allowed Values:
	Any integer.
	Default Value:
	1
SMS Service Provider	Definition:
	Specifies the name of the service provider.
	Allowed Values:
	A valid service provider name that appears in the list.
	If you want to use a different SMS listener vendor, contact AgilePoint Professional Services to request a new AgileConnector.
	Default Value:
	StrikeIron.

Field Name	Definition
Send SMS Notification to Users about Task Assignment	Definition: Specifies that the SMS Service AgileConnector sends an SMS notification to the participants about the task assignments. Allowed Values: Selected - Sends an SMS notification to the participants. Deselected - No SMS notification is sent. Default Value: Deselected
Test	Function: Verifies whether the specified account credential is valid.

Configuring the SPSyncModule Extension

This AgilePoint Server extension (AgileConnector) allows you to synchronize SharePoint site collection groups with AgilePoint groups automatically.

This extension is optional.

Prerequisites

- The AgilePoint System User (as defined in the AgilePoint Server Configuration utility) should be a SharePoint user.
- AgilePoint Server's Application Pool's Identity user account (as configured in IIS) needs to have read
 permissions to the SharePoint data.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the **Extension** tab, click on **Add**.
- Browse one of the following locations to open the file SPSyncModule.dll:
 - For IIS installations, this file is located in the bin folder under the AgilePoint Server installation folder.
 - For Windows Service installations, this file is located in the **bin** folder under the path provided in the **Location** field in Windows Server Manager for the Windows Service instance you want to configure.
- 3. Leave the **Impersonator** field blank.
- 4. Click OK.

Now you will need to configure the module to schedule the synchronization.

5. Click the **Configure** button, and specify the desired configuration settings.

In the configuration interface, you can specify the SharePoint site for which you want to synchronize the groups; you can also optionally provide the site prefix and group prefix. You can also specify the synchronization with the frequency of every day, week, or month and at a particular time of day starting with the day you set the schedule. The synchronization module also provides the option of registering the users automatically or sending an alert email to AgilePoint system user if there are members in the SharePoint groups that have yet to be registered in AgilePoint.

- 6. Provide a valid SharePoint Site URL, for example http://[hostname]:[port]/sites/MySite.
- 7. The Site Prefix field is optional.

In a case where two site collections are configured, then groups with a common name can be distinguished using this property. For example Site "A" has a group called "Employees" and Site "B" also has a group called "Employees". In AgilePoint, you can create two groups "SiteA_Employees" corresponding to Employees group in site A and "SiteB_Employees" corresponding to siteB's Employees. So while configuring Site A mention "SiteA_" in site prefix so that it will sync with "SiteA_Employees" during the synchronization process and for site B mention "SiteB_" in site prefix so that it sync's with "SiteB_Employees".

8. The "Group Prefix" field is optional.

This property is used in case a new group is created in SharePoint and you want that group to be created in AgilePoint. If a group prefix is not empty, then all the groups created in SharePoint starting with a Group prefix value will be created in AgilePoint during the Synchronization process. For example, the group prefix value is set as "GR_" then all the new groups in SharePoint starting with GR_ will be created and synced during the synchronization process.

9. The **Schedule** section is used to schedule the frequency of synchronization.

You can configure Synchronization frequency to sync daily (Every Day) at a particular time, or Weekly (Every Week), or Monthly (Every Month).

10. The **Option** section provides an option to select what action needs to be taken when a SharePoint group member is not an AgilePoint user. Either one can select to register user to AgilePoint automatically or send a notification to AgilePoint System user.

Group Member Synchronization Rules

- Only groups that have already been added into AgilePoint will be synchronized with SharePoint. New SharePoint groups will be added automatically to AgilePoint only if the group prefix value is not empty and the new SharePoint group name starts with a Group prefix value. The new groups will automatically be assigned to the default "Users" Role. If a group prefix value is empty, then new groups can be added manually through the Enterprise Manager interface.
- The changes of user members (adding or removing) in the SharePoint groups will be synchronized to AgilePoint but the changes in AgilePoint groups will NOT be synchronized back to the SharePoint groups.
- The synchronization only applies to member association (Add or Remove) within the groups. Group
 properties such as names and descriptions are NOT synchronized.
- When a new member is added to SharePoint group, this member will also be added to the corresponding AgilePoint group. If the actual user entity is not registered in AgilePoint yet, the user entity will be registered to AgilePoint automatically.

When a member is removed from SharePoint group, this member in the corresponding AgilePoint group will
also be removed. The actual user entity will NOT be removed from AgilePoint as the same user entity can
also be associated with other groups in the system.

User Synchronization Rules

Changes to the following SharePoint User properties will be synchronized to AgilePoint. Other properties will NOT be synchronized.

- Full Name
- Email Address
- Department
- Title
- Manager

Scheduling

The schedule of the synchronization is set through the module's configuration interface. The synchronization can be performed at a particular time of day with the frequency of every day, every week, or every month.

For example, if you schedule the synchronization to be performed at 2am on Jan. 1 and you also select **Every day** as the frequency, the synchronization will be started automatically at 2am on Jan 1, Jan 2, Jan 3, etc.

The following table summarizes the different ways that the schedule can be set for the synchronization.

Frequency	Time	1st Sync	2nd Sync	3rd Sync	4th Sync	5th Sync
Every Day	2am	Jan. 1	Jan. 2	Jan. 3	Jan. 4	Jan. 5
Every Week	2am	Jan. 1	Jan. 8	Jan. 15	Jan. 22	Jan. 29
Every Month	2am	Jan. 1	Feb. 1	March. 1	April. 1	May. 1

The synchronizations typically happen within five minutes of the scheduled time. For example, if the scheduled time is 2am, the actual synchronization could happen between 1:55am to 2:05am.



Note: The scheduling pattern (daily, weekly, or monthly) and scheduling time should be the same for multiple AgileConnectors of the same type.

Exception Handling

This module also provides exception handling for the scheduling. In the event that your server is down during the scheduled synchronization, as soon as your server is back online, the synchronization will be automatically kicked off. After that, the next synchronization will resume the original schedule.

Log Files



Note: The SharePoint Groups Synchronization module also writes log messages to the SPSyncModule.log file. The SPSyncModule.log file can also be found at the AgilePointServer\log folder.

This log file contains detail information about each synchronization operation, such as the status of each group, or what users were unable to be registered to AgilePoint.

The following is an example of the log message in the ActiveDirectorySynchronizer.log file:

```
3/1/2005 5:51:49 PM>> Synchronization has started
    to perform on 3/1/2005 5:51:47 PM
Synchronizing Group 'Employees', SharePoint site URL =
    http://r61i-01:8000 Registering user 'MYDOMAIN\Test1' to
    AgilePoint. User full name: Test1
```

Notifications

In addition to log files that keep track of the synchronization statuses, the synchronization module also provides email notification capability. Email notification is sent out to the AgilePoint System User with information about the synchronization. This will allow the system user to determine if there is a need to manually synchronize the groups or users in the event of failed synchronization.

Configuration Interface

SharePoint Section

- SiteURL Provide a valid SharePoint site URL, for example http://[hostname]:[port]/sites/MySite
- Site Prefix This property is optional. In case two site collections are configured then groups with common name can be distinguished using this property. For example Site "A" has group called "Employees" and Site "B" also has a group called "Employees". In AgilePoint you can create two groups "SiteA_Employees" corresponding to Employees group in site A and "SiteB_Employees" corresponding to siteB's Employees. So while configuring Site A mention "SiteA_" in site prefix so that it will sync with "SiteA_Employees" during synchronization process and for site B mention "SiteB_" in site prefix so that it sync's with "SiteB_Employees"
- **Group Prefix** This property is optional. This property is used in case a new group is created in SharePoint and you want that group to be created in AgilePoint. If a group prefix is not empty then all the groups created in SharePoint starting with Group prefix value will be created in AgilePoint during Synchronization process. For example, the group prefix value is set as "GR_" then all the new groups in SharePoint starting with GR_ will be created and synced during synchronization process.

Option Section


This section provides an option to select what action needs to be taken when a SharePoint group member is not an AgilePoint user. Either one can select to register user to AgilePoint automatically or send a notification to AgilePoint System user.

Schedule Section

This section is used to Schedule the frequency of Synchronization. One can configure Synchronization frequency to sync daily (Every Day) at particular time, or Weekly (Every Week) or Monthly (Every Month).

Configuration for SharePoint Groups Synchronization Window

Specifies the configuration details for synchronizing SharePoint groups with AgilePoint groups.




Prerequisites

Before configuring, you must enable the SPSync Module AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select SPSyncModule.
- 4. Click Configure.



Field Name	Definition
	Yes
	Example:
	http://mysharepoint:8000/sites/\${mysite}
Site Prefix	Function: Distinguishes a site with the specified name prefix in two site collections during the synchronization process. Allowed Values: A single line of text with no spaces. Default Value: None Example: Two sites, Site A and Site B, each have a group called "Employees." In AgilePoint, you can create two groups: "SiteA_Employees" and "SiteB_Employees." While configuring site A, enter "SiteA_" in the Site Prefix so this site syncs with
	"SiteA_Employees." While configuring Site B, enter "SiteB_" in Site Prefix so this site syncs with "SiteB_Employees".
Group Prefix	Function: Indicates that all the groups in SharePoint starting with a specified prefix in the group name are created in AgilePoint during the synchronization process.
	Allowed Values:
	A single line of text with no spaces.
	Default Value:
	None
	Example:
	If the group prefix value is set as GR_ then all the new groups in SharePoint starting with GR_ will be created and synced during the synchronization process.
Schedule	Function: The frequency for SharePoint synchronization. Synchronization can occur every day, week, or month, at a particular time or day.

Field Name	Definition
If Active Directory group member is not AgilePoint user	Definition: Specifies what actions to take if a member of your Active Directory is not a registered AgilePoint user.
	Allowed Values:
	Register user to AgilePoint automatically Creates an AgilePoint account for the user using their Active Directory information.
	 Send email to AgilePoint system user, and do not take any action - Does not create an AgilePoint account for the Active Directory user, but sends a notification email to the AgilePoint system user account.
	Default Value:
	Register user to AgilePoint automatically
Sync all Lync IDs with email IDs	Definition: Synchronizes all of your users' Lync IDs with their email IDs. This synchronization occurs each time and Active
	Directory synchronization occurs. AgilePoint recommends using this option only if all of your users' messaging IDs and email IDs are the same.
	Allowed Values:
	 Selected - Synchronizes Lync IDs with users' email IDs.
	Deselected - Does not synchronize Lync IDs with users' email IDs.
	Default Value:
	Deselected
Sync all Yammer IDs with email IDs	Definition:
	Synchronizes Yammer IDs with AgilePoint users' email IDs. This synchronization occurs each time and Active Directory synchronization occurs. AgilePoint recommends using this option only if all of your users' messaging IDs and email IDs are the same.
	Allowed Values:
	Selected - Synchronizes Yammer IDs with users' email IDs.
	Deselected - Does not synchronize Yammer IDs with users' email IDs.

Field Name	Definition
	Default Value:
	Deselected

Yammer Hashtag AgileConnector

The Yammer Hashtag AgileConnector enables process participants to initiate process instances using Yammer hashtags.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.

Enabling the Yammer Hashtag AgileConnector

To enable the Yammer Hashtag AgileConnector, do the following.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.

Instructions

- 1. On the **Extensions** tab, click **Add**.
- 2. In the **Impersonator** field, enter the AgilePoint user name that is used to connect to your email server. By default, this is the AgilePoint Service Account.
- 3. Browse to the assembly [AgilePoint Server installation folder]\bin \AgilePoint.AgileConnector.YammerHashTag.dll.

Configuring the Yammer Hashtag AgileConnector

To configure the Yammer Hashtag AgileConnector, do the following.

Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Yammer Hashtag AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Configuration.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select YammerHashTag.
- 4. Click Configure.

Instructions

- 1. On the **Yammer Hashtag Configuration** window, select the schedule you want to start a process instance after the hashtag is posted to Yammer:
 - **Fixed Time** A time of day after the hashtag appears.
 - For example, if the fixed time is set to Hour 22 and Minute 15, the process will start at the next occurrence of 10:15 pm.
 - **Time Frequency** A time interval following the time the hashtag is posted.
 - For example, if this is set to 15 Minutes, the process will start 15 minutes after the hashtag is used.
- 2. Click Next.
- 3. On the Yammer Hashtag Configuration window, click Add (+).
- 4. On the **Add Yammer Definition** window, in the **Yammer Definition Name** field, enter an identifying name for your Yammer hashtag configuration settings.
- 5. Complete the fields on the Yammer Hashtag Configuration window as required.

For more information, see the following topics:


- Yammer HashTag Configuration Window Yammer Credentials Tab
- Yammer HashTag Configuration Window Hash Details Tab
- Yammer HashTag Configuration Window Process Initiation Configuration Tab

Configuration Windows

The following topics provide details about the configuration windows for this AgileConnector.

Yammer HashTag Configuration Window - Yammer Credentials Tab

Identifies your Yammer application credentials.



Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Yammer Hashtag AgileConnector.

Navigation


- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select YammerHashTag.
- 4. Click Configure.
- On the Yammer Hashtag AgileConnector Configuration window, set the schedule to initiate your process instance.
- 6. Click Next.

Field Name	Definition
Yammer Definitions	Definition:

Field Name	Definition
	A group of configuration settings for initiating a specified process instance using a specified Yammer connection.
	You can select a Yammer definition to modify, or click Add to create a new Yammer definition to add to the list.
	Allowed Values:
	The list of your defined Yammer definitions.
	Default Value:
	None
Add	Function:
	Creates new Yammer definition.
Remove	Function:
	Deletes the selected Yammer definition.
Application Name	- a
, pplication raine	Definition:
	Specifies a unique name for your application. This key can represent any identifying value for your
	application.
	Allowed Values:
	An alphanumeric string.
	Default Value:
	None
Configuration Key	Definition:
	Specifies the unique authentication key for your application. This key is associated with an your administrator user account.
	This key can represent any identifying value for your application.
	Allowed Values:
	An alphanumeric string.
	Default Value:
	None
	Custom Attributes:
	No

Yammer HashTag Configuration Window - Hash Details Tab

Specifies the combination of Yammer hashtags and recipients that are used to initiate your process.



Prerequisites

- The user interface for this feature is available in English only.
- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Yammer Hashtag AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the **Extensions** tab, select **YammerHashTag**.
- 4. Click Configure.
- On the Yammer Hashtag AgileConnector Configuration window, set the schedule to initiate your process instance.
- 6. Click Next.


Field Name	Definition
Yammer Definitions	Definition:

Field Name	Definition
	A group of configuration settings for initiating a specified process instance using a specified Yammer connection.
	You can select a Yammer definition to modify, or click Add to create a new Yammer definition to add to the list.
	Allowed Values:
	The list of your defined Yammer definitions.
	Default Value:
	None
Add	Function:
	Creates new Yammer definition.
Remove	Function:
	Deletes the selected Yammer definition.
Group / User	Definition:
	Specifies where to listen for messages that include the Yammer hashtag key posted to the specified group, or the administrator user.
	Allowed Values:
	 Group - Listens for the posted message to specified group.
	User - Listens for the posted message to the administrator user account associated with the application name and configuration key.
	Default Value:
	Group
HashTag	Definition:
	Specifies the Yammer hashtag which, when posted to the specified user or group, will initiate your process.
	Allowed Values:
	A single line of text with prefix # symbol and no space.
	Default Value:
	None

Field Name	Definition
Group	Definition: Specifies the group name which is used in the Yammer application. Allowed Values: A valid Yammer group name. Default Value: None
Add (+)	Function: Creates a new Yammer hashtag key.
Remove (-)	Function: Deletes the selected Yammer hasttag.

Yammer HashTag Configuration Window - Process Initiation Configuration Tab

Specifies the behavior when a process instance is initiated using a Yammer hashtag.



Prerequisites

The user interface for this feature is available in English only.

- AgilePoint Server installed in Windows Service mode.
- Before configuring, you must enable the Yammer Hashtag AgileConnector.

Navigation

- 1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Configuration**.
- 2. On the AgilePoint Server Configuration Tool window, click the Extensions tab.
- 3. On the Extensions tab, select YammerHashTag.
- 4. Click Configure.
- 5. On the **Yammer Hashtag AgileConnector Configuration** window, set the schedule to initiate your process instance.
- 6. Click Next.

Field Name	Definition
Yammer Definitions	Definition:
	A group of configuration settings for initiating a specified process instance using a specified Yammer connection.
	You can select a Yammer definition to modify, or click Add to create a new Yammer definition to add to the list.
	Allowed Values:
	The list of your defined Yammer definitions.
	Default Value:
	None
Add	Function:
	Creates new Yammer definition.
Remove	Function:
	Deletes the selected Yammer definition.
SharePoint / Non-SharePoint	Definition:
	Specifies whether your process is associated with a SharePoint list.
	Allowed Values:
	 SharePoint - Specifies that your process is associated with a SharePoint list. This option allows you to associate Yammer variables with


Field Name	Definition
	SharePoint list columns associated with your process.
	 Non-SharePoint - Specifies that your process is not associated with a SharePoint list. This option allows you to associate Yammer variables with custom attributes from a non- SharePoint process.
	Default Value:
	Non-SharePoint
SharePointListUrl / Process Definition	Definition: Specifies the process model you want to initiate.
	Allowed Values:
	 SharePoint list URL - Enter the SharePoint list URL associated with the AgilePoint process you want to initiate.
	In SharePoint, ensure your SharePoint list is associated with a workflow that initiates your AgilePoint process.
	 Process Definition - Select the process model you want to initiate.
	Default Value:
	None
Custom Field	Definition:
	Specifies to a variable to map from your process to a Yammer variable.
	Allowed Values:
	 For a SharePoint process, to select name of a custom SharePoint list column as custom attribute do the following:
	1. Click Connect ().
	On the Connect to SharePoint window, enter the user account you want to use to connect to SharePoint.
	For more information, see Logging on to SharePoint from a Process Template or AgileShape.
	Select the name of the custom SharePoint list column.

For a non-SharePoint process, specify a process attribute you want to map to the Yammer field. Default Value: None Yammer Field Definition: Specifies the standard Yammer variable you want	
Yammer Field Definition: Specifies the standard Yammer variable you wan	
Yammer Field Definition: Specifies the standard Yammer variable you wan	
Specifies the standard Yammer variable you wan	
	t to
map with your process variable.	
Allowed Values:	
• MESSAGE_ID	
• GROUP_NAME	
• SENDER_ID	
REPLIED_TO_ID	
• CREATED_AT	
NETWORK_ID	
• MESSAGE_TYPE	
SENDER_TYPE	
• URL	
• WEB_URL	
BODY_PARSED_TEXT	
BODY_PLAIN_TEXT	
BODY_RICH_TEXT	
• THREAD_ID	
SENDER_FULL_NAME	
SENDER_DEPARTMENT	
SENDER_EMAIL	
CLIENT_TYPE	
CLIENT_URL	
• SYSTEM_MESSAGE	
DIRECT_MESSAGE	
CHAT_CLIENT_SEQUENCE	
CONTENT_EXCERPT	
• LANGUAGE	
Default Value:	
None	

Field Name	Definition
Add (+)	Function: Creates a new custom field.
Remove (-)	Function: Deletes the selected custom field.

Work Calendar Window

This window allows you to configure the "business hours" that are used by certain AgilePoint technologies that use "business time". E.g. When a Manual or Delay AgileShape is configured to use "business time", the settings on this window determine how the specified interval of "business time" corresponds to real (absolute) time.



AgilePoint Server Manager Configuration in Windows Service Mode

This topic provides information about the configuration file for AgilePoint Server running in Windows Service mode. This is the configuration file for the windows service version of AgilePoint Server. It stores information about the services configured in AgilePoint Server Manager.

Location: [AgilePoint Server installation folder]\APServerManagerConfig.cfg

Prerequisites

AgilePoint Server installed in Windows Service mode.

Example

AgilePoint Deployment Services

The AgilePoint Deployment Utility is used to package and migrate AgilePoint Process Models and associated AgilePart/AgileWork assemblies amongst the different AgilePoint Server environments (e.g. Development, Testing, Staging, and Production). This tool can also be used to backup and restore Process Models and associated AgilePart/AgileWork assemblies.

Installing AgilePoint Deployment Services is optional. For a fresh installation and upgrade, AgilePoint Deployment Services is installed as a separate component via the **AgilePoint Utilities and Other Support Files** section of the installer.

The AgilePoint Deployment Services consists of the following components:

- AgilePoint Deployment Service
- AgilePoint Deployment Utility

AgilePoint Deployment Service

The AgilePoint Deployment Service is a Windows service that runs on the AgilePoint Server machine, and provides a WCF communication channel between the server and the client.

AgilePoint Deployment Utility

The AgilePoint Deployment Utility is used to package and migrate AgilePoint Process Models and associated AgilePart/AgileWork assemblies amongst the different AgilePoint Server environments (e.g. Development, Testing, Staging, Production). This tool can also be used to backup and restore Process Models and associated AgilePart/AgileWork assemblies.

Opening the AgilePoint Deployment Utility

To open the AgilePoint Deployment Utility:

1. Click Start > All Programs > AgilePoint > AgilePoint Deployment Utility.

Adding an AgilePoint Server

To expose process templates and associated dependencies that are deployed to an AgilePoint Server, first add the AgilePoint Server to the server collection. Two things are accomplished at this stage; the first is to test the connection to the AgilePoint Server, the second is to create a connection to the AgilePoint Server. After the information about the AgilePoint Server is gathered, the AgilePoint Deployment Service will validate the connection, and the certification of the user.

To add an AgilePoint Server:

- 1. From the AgilePoint Explorer tab, click the **Add** button.
- 2. In the **Display Name** field, type a Display Name that specifies the name of the AgilePoint Server that will be displayed in the AgilePoint Server Collection list.

- In the Server field, select either Host Name or IP Address and enter the information about the AgilePoint Server as necessary.
- 4. In the **Port** field, type the Port number for the WCF Service (the default is 8917). The port number can be found and changed in the file [AgilePoint Deployment Service installation folder]\approx apds.exe.config.
- 5. In the **Domain** field, type the Domain Name for the AgilePoint Server.
- 6. In the **Username** field, type the AgilePoint Server System username.
- 7. In the **Password** field, type the password for the AgilePoint Server System user.
- 8. Click **Test Connection** to test the connection to the AgilePoint Server. If the test connection is successful, click **OK**.
- 9. The AgilePoint Deployment Utility appears with the AgilePoint Server added.
- 10. Repeat the process to add the desired AgilePoint Servers to the AgilePoint Deployment Utility.

Removing an AgilePoint Server

For one reason or another, an AgilePoint Server may need to be removed from the collection if it is no longer used.

To remove an AgilePoint Server:

1. From the AgilePoint Explorer tab, select the AgilePoint Server for which you would like to remove and click the **Remove** button on the toolbar. The AgilePoint Server is removed from the list.

Backing up a Process Model and Associated Dependencies

The Backup function allows for Process Models and associated dependencies on an AgilePoint Server to be backed up into a package file. The process definition will be saved as an XML file, and the associated dependencies will be copied from GAC. After all items are gathered, a package file (.odp) will be created and saved to the location specified. The package file can then be restored in a recovery scenario.

To backup a process model and associated dependencies:

- 1. From the **AgilePoint Explorer** tab, select the AgilePoint Server for which you would like to backup a Process Model and associated dependencies from and click the **Backup** button on the toolbar. The Backup Process Definition Wizard appears.
- 2. Click Next.
- 3. Select the Application(s) type(s) for which to backup and click **Next**.
- 4. Select the Process Model(s) and click **Next**.
- 5. Select the AgileParts and AgileWorks for which to backup and click **Next**.
- 6. Type the file path of browse and select the folder location for which to save the package file and click **Next**.
- 7. Once the backup has been completed successfully, click **Finish**. The package file is saved to the folder specified as an .odp package file that can then be later restored as needed.

Restoring a Process Model and Associated Dependencies

The Restore function allows for the package file (i.e. Process Model and associated dependencies) to be restored on an AgilePoint Server.

To restore a process model and associated dependencies:

- From the AgilePoint Explorer tab, select the AgilePoint Server for which you would like to backup a Process Model and associated dependencies from and click the **Backup** button on the toolbar. The Restore Process Definition Wizard appears.
- 2. Add the desired package file(s) (.odp) and click Next.
- 3. Once the restore has been completed successfully, click **Finish**.

Migrating a Process Model and Associated Dependencies

The following provides instructions for migrating a Process Model and associated dependencies from one AgilePoint Server to another.

To migrate a Process Model and the associated dependencies:

In this example, the Document Approval Process Model and associated dependencies will be migrated from the AgilePoint Server on the Dimension4700-01machine to the AgilePoint Server on the ibmt61-005 machine.

- 1. Right-click on the AgilePoint Server host machine name that contains the Process Model and dependencies for which you would like to export.
- Click the Import Export button. The Export & Import Process Definition Wizard appears.
- Click Next.
- 4. Select the application type(s) (ASP.NET or SPSIntegration).
- 5. Select the Process Template(s).
- 6. Click **Next**. The system automatically selects all the dependencies for the Process Templates.
- 7. Click **Next**. The list of Process Templates appears.
- 8. Click Next.
- 9. Select the target machine where AgilePoint Server is installed.
- Click Next. The system moves the Process Template and associated dependencies to the target AgilePoint Server.
- 11. Click Finish.

Rolling back a Process Model and Associated Dependencies

The rollback function can be used if a Process Model and associated dependencies fail to be deployed to a target AgilePoint server, a new project fails to be deployed, or a package file fails to be restored. The AgilePoint Deployment Service records the information in a XML file and provides a way to rollback the migration.

To rollback a Process Model and the associated dependencies:

- From the AgilePoint Explorer tab, select the AgilePoint Server that contains the Process Model and associated dependencies that failed to be migrated to a target AgilePoint server, the project failed to be deployed, or a package file failed to be restored and click the Rollback button on the toolbar. The Rollback Process Definition Wizard appears.
- 2. Click Next.
- 3. Select the item(s) (i.e. Process Model and dependencies, project, or package files) and click **Next**.
- 4. Once the rollback has been completed successfully, click **Finish**.

Creating a Project

If a new edition of a process definition is to be deployed to an AgilePoint Server, a new project can be created. The project includes the Process Model that will be saved in the folder location you have specified. The Process Model should be an XML file.

To create a new project

- Click the Local Projects tab and click Create.
- 2. In the **Name** field, type a name for the project.
- 3. In the **Location** field, type a file path or browse and select the folder for which to store the project collection.
- 4. In the **Description** field, type a description for the process.
- 5. In the **Process** field type a file path to the XML file for a Process Model to add to the project or browse and select it.
- 6. Click OK.



Note: The Process Model must be a XML file.



Note: AgilePoint Envision should NOT be running when creating a project.

Project Functions

Add Project

Once a project is created, you can add a project to the project collection from another place by right-clicking on the project collection name and selecting **Add Project**.

Remove Project

Once a project is created, you can remove a project from the project collection by right-clicking on the project name and selecting **Remove Project**.

Add a Process

Once a project is created, you can add a process to the project by right-clicking on the project and selecting **Add Process**.

Remove a Process

Remove a process from a project by right-clicking on the project and selecting **Remove Process**.

Analyze AgilePart

Once a project is created, you can analyze AgileParts for a Process Model by right-clicking on a project and selecting **Analyze AgilePart**. If an AgilePart has been unintentionally removed, this function will allow you to get all AgileParts associated with the Process Model.

Add AgilePart Assembly

Once a project is created, you can add an AgilePart assembly for a Process Model by right-clicking on an assembly and selecting **Add AgilePart Assembly**.

Exclude AgilePart Assembly

Once a project is created, you can remove an AgilePart assembly for a Process Model by right-clicking on an assembly and selecting **Exclude AgilePart Assembly**.

Analyze AgileWork

Once a project is created, you can analyze AgileWorks for a Process Model by right-clicking on a project and selecting **Analyze AgileWork**. If an AgileWork has been unintentionally removed, this function will allow you to get all AgileWorks associated with the Process Model.

Add AgileWork Assembly

Once a project is created, you can add an AgileWork assembly for a Process Model by right-clicking on an assembly and selecting **Add AgileWork Assembly**.

Exclude AgileWork Assembly

Once a project is created, you can remove an AgileWork assembly for a Process Model by right-clicking on an assembly and selecting **Exclude AgileWork Assembly**.

Analyze Dependency

Once a project is created, you can analyze dependencies for an assembly by right-clicking on an assembly and selecting **Analyze Dependency**. If a dependency has been unintentionally removed, this function will allow you to get all dependencies associated with the assembly.

Add Dependency Assembly

Once a project is created, you can add a dependency assembly for an assembly by right-clicking on an assembly and selecting **Add Dependency Assembly**.

Exclude Dependency Assembly

Once a project is created, you can remove an dependency assembly for an assembly by right-clicking on an assembly and selecting **Exclude Dependency Assembly**.

Opening a Project

This function allows you to add an existing project to the project collection for editing.

To open a project:

- 1. Click the Local Projects tab and click Open.
- 2. Select the project to add or click **More** and browse to select it.

Saving a Project

After a project collection has been created or edited, it must be saved. All items of a project collection including the Process Model XML file and associated dependencies will be saved. When saving a project collection, you have the option to change the name as desired.

Packaging a Project

This function allows you to package an entire project collection and save it to the client machine for archive purposes.

Deleting a Project or Project Collection

This function allows you to delete a project or project collection from the Deployment Services Utility.

Closing Projects

This function allows you to close a project or project collection.

Deploying a Project

This function allows you to deploy a project to a target AgilePoint Server machine.

To deploy a project:

- 1. Click the Local Projects tab and click Deploy. The Deploy Project Wizard appears.
- 2. Click Next.
- 3. Select the project(s) to add and click Next.
- 4. Select the target AgilePoint Server and click Next.
- 5. Once the deployment has been completed successfully, click Finish.

Viewing Deployment History

This function allows you to view deployment history interaction (e.g. what operations occurred and the result) on an AgilePoint Server machine.

To view deployment history:

- 1. Click the **Deployment History** tab.
- 2. Expand the AgilePoint Server for which you would like to view deployment history.
- 3. Click the date icon to view the deployment history.

To delete deployment history, right-click on a date icon and select **Delete History**.

AgilePart Deployment Wizard Utility

The AgilePart Deployment Wizard is a utility application that allows you to register custom AgilePart assemblies with AgilePoint Server so that those assemblies can be downloaded from AgilePoint Envision and used by AgilePoint Server's workflow engine at run time.

Navigation

 To open the AgilePart Deployment Wizard, Click Start > All Programs > AgilePoint > AgilePart Deployment Wizard.

Instructions

- 1. On the AgilePart Deployment Wizard, click Add.
- 2. On the **Deploy AgilePart** window, in the **Assembly** section, click the **Ellipse** button to select the required custom AgilePart dll.
- 3. Click OK.

Performance Tracing Utility

The Performance Tracing utility allows you to report on performance of custom components such as custom AgileParts, AgileWorks, AgileConnectors, AgileStubs, or Web Services. The performance criteria is based on milliseconds, for example you can write a query to return the most time consuming AgileParts. To use this utility, you will need a database that includes a table called WF_PERF_TRACES (it is not recommended to add this table to the AgilePoint database). You will also need to add a PerfTrace.config XML file to the root level folder where AgilePoint Server is installed (e.g. c:\inetpub\wwwroot\AgilePointServer\). The location of AgilePoint Server can be determined from the registry.

To use the utility to perform performance tracing:

1. Create a new table called **WF_PERF_TRACES** in a database as below. It is not recommended to use the AgilePoint database for this table.

```
SET ANSI_NULLS ON

GO

SET QUOTED_IDENTIFIER ON

GO

SET ANSI_PADDING ON

GO

CREATE TABLE [WF_PERF_TRACES](
[SOURCE] [varchar](1024) NULL,
[CATEGORY] [int] NULL,
[OBJECT_ID] [varchar](256) NULL,
[TIME_STARTED] [datetime] NULL,
[TIME_SPAN] [int] NULL
) ON [PRIMARY]

GO

SET ANSI_PADDING OFF
```

A sample query may return results as shown below:

	SOURCE	CATEGORY	OBJECT_ID	TIME_STARTED	TIME_SPAN
1	#AgilePart:Ascentn.AgileP	0	b81fad11691e4ce7a6a92	2007-08-03 15:56:47.350	171736
2	#AgilePart:Ascentn.AgileP	0	77fb50b240dc422ebf6e9e	2007-08-03 16:08:01.440	83109
3	#AgilePart:Ascentn.AgileP	0	0e5a6fc77c6349f3a86564	2007-08-03 19:22:50.990	54468
4	#AgilePart:Ascentn.AgileP	0	5342b4a43d764c4a8b3ca	2007-08-01 17:25:30.700	54338
5	#AgilePart:Ascentn.AgileP	0	e3f8d99521bd481d8e6c3	2007-08-01 19:26:36.017	47184
6	#AgilePart:LabOneAgilePar	0	3621C4E80B004EBA97E0	2007-07-20 03:38:29.173	35541
7	#AgilePart:LabOneAgilePar	0	C19819A8BC6A4FAEA0A	2007-07-20 03:38:29.253	35460
8	GetEvent	3	T42Z\Administrator	2007-08-05 21:22:11.120	31124
9	#AgilePart:Ascentn.AgileP	0	e0e9a3590dd94b1984be3	2007-08-03 17:16:47.443	20229
10	#AgilePart:Ascentn.AgileP	0	b81fad11691e4ce7a6a92	2007-08-03 16:00:28.307	16473

2. In a text editor, create a new file with the following content:, and save it with the name **PerfTrace.config**.

3. Save the file to the following path and file name:

```
[AgilePoint Server installation folder]\PerfTrace.config
```

- 4. Configure **PerfTrace.config** as follows:
 - a. Within the **Database** section, enter the database vendor and connection string for your performance tracking database.
 - b. The **Filter** section allows you to add the categories for which you want to report on. The categories that are available include:
 - AgilePart Reports on all AgilePart data.
 - **ProcessEventHandler** Reports on AgileWork and AgileStub data.
 - TrackingEvent Reports on AgileConnector data.
 - WebService Reports on Web Service data.

When doing the reporting, a few of the filtering options that are available include:

- Exclude Categories To exclude one or more of the categories, remove the category from the PerfTrace.config file. For example, remove the <Category>WebService</Category> to tell AgilePoint Server to exclude Web Service tracing data from being recorded to the database.
- When writing your SQL, each category has been assigned a numerical identifier for filtering. This allows you to report only on a certain category. Each category is identified as follows:
 - AgilePart 0.
 - ProcessEventHandler 1.
 - TrackingEvent − 2.
 - WebService 3.

A couple of sample query statements are shown below:

```
select * from WF_PERF_TRACES where source like
'%Sample%' order by time_span desc
select * from WF_PERF_TRACES
where category = 0 and source like '%Move%'
order by time span desc
```

A sample query may return results similar to below:

	SOURCE	CATEGORY	OBJECT_ID	TIME_STARTED	TIME_SPAN
1	#AgilePart:Ascentn.AgileP	0	b81fad11691e4ce7a6a92	2007-08-03 15:56:47.350	171736
2	#AgilePart:Ascentn.AgileP	0	77fb50b240dc422ebf6e9e	2007-08-03 16:08:01.440	83109
3	#AgilePart:Ascentn.AgileP	0	0e5a6fc77c6349f3a86564	2007-08-03 19:22:50.990	54468
4	#AgilePart:Ascentn.AgileP	0	5342b4a43d764c4a8b3ca	2007-08-01 17:25:30.700	54338
5	#AgilePart:Ascentn.AgileP	0	e3f8d99521bd481d8e6c3	2007-08-01 19:26:36.017	47184
6	#AgilePart:LabOneAgilePar	0	3621C4E80B004EBA97E0	2007-07-20 03:38:29.173	35541
7	#AgilePart:LabOneAgilePar	0	C19819A8BC6A4FAEA0A	2007-07-20 03:38:29.253	35460
8	GetEvent	3	T42Z/Administrator	2007-08-05 21:22:11.120	31124
9	#AgilePart:Ascentn.AgileP	0	e0e9a3590dd94b1984be3	2007-08-03 17:16:47.443	20229
10	#AgilePart:Ascentn.AgileP	0	b81fad11691e4ce7a6a92	2007-08-03 16:00:28.307	16473



Note: It is not necessary to restart IIS upon making changes to the configuration file. AgilePoint Server will begin recording this tracing data to the database within 10-30 seconds. You can delete this file or rename it to stop this service.

APADM Command Line Utility

This topic provides examples using commands for the APADM SharePoint command line utility. The APADM application is a command line utility that can be used to perform some administrative tasks from the command line.

Prerequisites

- To use the ExecutionTimeout argument, you must have a release that includes Intermediate Fix 08.0081.02.
- To use the SyncSocialAccounts argument, you must have AgilePoint v5.0 R2 with Intermediate Fix 08.0082.01.

Navigation

1. In a command prompt, change directories to [AgilePoint Server installation folder]\Tools

Instructions

1. Run the following commands as required, using the following format:

apadm.exe [command] [arguments]

Command	Required Arguments	Optional Arguments	Example
-help			
-adduser	[LDAP path][AgilePoint Server URL]	 ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation. SyncSocialAccounts 	
		- Synchronizes users' email IDs with their Yammer and Lync IDs.	adduser LDAP:// dc=tusca,dc=com http://localhost/ AgilePointServer ExecutionTimeout=100
-archive	 [days] or [process instance ID] or [ProcessDefinitionNation In Its Image	• -Y - Supresses the interactive ame: Proceed with the action.	The following example archives all processes that were completed or canceled 10 days ago. • apadm -archive
		 ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation. 	10 http://localhost/ AgilePointServer The following example archives the process with the specified process instance ID.

Command	Required Arguments	Optional Arguments	Example
			 apadm -archive 501630F1C09743dbBA25FAC9C3I http://localhost/ AgilePointServer apadm -archive 10 http://localhost/ AgilePointServer -Y ExecutionTimeout=100
-restore	 [process instance ID] or [ProcessDefinitionN [AgilePoint Server URL] 	ExecutionTimeout = [seconds] - ame:BroccesssInstiameName value, in seconds, for the operation.	 apadm -restore 501630F1C09743dbBA25FAC9C3I http://localhost/ AgilePointServer apadm -restore ExpenseReport:JohnSmith-01-20-2 http://localhost/ AgilePointServer ExecutionTimeout=100
-syncgm	 [LDAP path] [authentication domain name] [AgilePoint Server URL] 	 [retry count] - An integer that specifies a number of times to retry the operation before quitting. ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation. SyncSocialAccounts - Synchronizes users' email IDs with their Yammer and Lync IDs. 	apadm - syncgm LDAP:// dc=tusca,dc=com TUS http://localhost/ AgilePointServer In the following example, if synchronization fails, it retries 5 times as specified in the optional last parameter. apadm - syncgm LDAP:// dc=tusca,dc=com TUS http://localhost/ AgilePointServer 5 ExecutionTimeout=100
-rmprocdef	 [process definition name] [AgilePoint Server URL] 	 -Y - Supresses the interactive confirmation to proceed with the action. ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation. 	 apadm -rmproc PurchaseRequest http://localhost/ AgilePointServer apadm -rmproc PurchaseRequest http://localhost/ AgilePointServer -Y ExecutionTimeout=100

Command	Required Arguments	Optional Arguments	Example
-mgproc	 [process migration instruction XML file] [AgilePoint Server URL] 	-NoSchemaMigrate - Stops upgrading the schema to the latest updated schema. -Run - Keeps the process running, even if an error occurs while running the operation. By default, if an error occurs, the process moves to a suspended state. ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation.	 apadm -mgproc PurchaseRequest http://localhost/ AgilePointServer apadm -mgproc PurchaseRequest http://localhost/ AgilePointServer - NoSchemaMigrate -Run ExecutionTimeout=100
-sysinfo	[AgilePoint Server URL]	ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation.	 apadm -systeaminfo http://localhost/ AgilePointServer apadm -systeaminfo http://localhost/ AgilePointServer ExecutionTimeout=100
-publishprocdef	 [AgilePoint Server URL] [folder] or [file] [release date] 	ExecutionTimeout = [seconds] - Specifies a timeout value, in seconds, for the operation.	In this example, abc is a folder that contains XML files of process definition that need to be published and scheduled to be released on 1/20/2011. apadm - publishprocdef http://localhost/AgilePointServer abc 1/20/2011 apadm - publishprocdef http://localhost/AgilePointServer abc 1/20/2011 ExecutionTimeout=100 In this example, expensereport.xml is an XML file of process

Command	Required Arguments	Optional Arguments	Example
			definition that needs to be published.
			 apadm - publishprocdef http://localhost/ AgilePointServer expensereport.xml
-analyzeclusterlog	• [cluster log file]	• ExecutionTimeout = [seconds] - Specifies a timeout	apadm - analyzeclusterlog 20110521T043713Cluste
		value, in seconds, for the operation.	 apadm - analyzeclusterlog 20110521T043713Cluste ExecutionTimeout=100

APADM Archive Database Command

The APADM utility can be used to manually initiate archiving of AgilePoint Server data to the archive database. Archiving the workflow data will move the data for old processes from the main workflow database to an archive database. Old processes are those that have been Canceled or Completed for at least a specified minimum number of days.

Prerequisites

- Configure a connection to an archive database using the AgilePoint Server Configuration utility.
- Log on to Windows using a user account with the access rights "Archive Process Instance" in AgilePoint.

Navigation

1. Open the APADM Command Line Utility:

```
[AgilePoint Server installation folder]\Tools\apadm.exe
```

Instructions

1. Run the archive database command:

```
apadm -archive [days] [AgilePointServer URL]
```

The following is an example of using the utility to archive all processes that were completed or canceled at least 170 days ago:

```
D:\>apadm -archive 170 http://[hostname]/AgilePointServer
Connecting AgilePoint Server...You currently logon as 'MYDOMAIN\admin'
Query AgilePoint database...12 process(es) can be archived.
Please enter <Y> to continue, otherwise stop...y
Archiving process '/sites/AgilePointFinancialSite/
ExpenseReport_InfoPath/ER-2005-0032.xml#1'...Done ( 0.334(s))
```

APADM Synchronize Active Directory Command

The apadm.exe utility can be used to manually initiate a synchronization of AgilePoint Server's users and groups with Active Directory. (This is a manual alternative to the ADSyncModule server extension.)

APADM Bulk Migration Command

The apadm.exe utility can be used to do a bulk migration of process instances. For more information, see Migrating a Process Model and Associated Dependencies in the Documentation Library.

AgilePoint Server Monitor Service

Prerequisites

- AgilePoint Server installed in Windows Service mode.
- AgilePoint Server running in IIS mode.

The AgilePoint Server Monitor is a Windows service application that can be used to monitor the AgilePoint Server application, and to automatically restart the application if IIS should stop and/or recycle the application's process. This service can be useful if you want to prevent your end users from experiencing the occasional delay that may occur during the first use of the application after IIS has recycled the application's worker process.

When running, the service makes a simple request to the AgilePoint Server application once per minute in order to ensure that the application is still initialized and running. If the application isn't running, the request will cause IIS to start it.



Note: The utility will be automatically installed to Windows' Services console when installing AgilePoint Server v3.2.0.2 or later. However, when upgrading from v3.2.0.1 or earlier, you will need to use the .NET Framework's InstallUtil.exe utility to manually register the apsyrmon.exe executable.

The executable is located in your AgilePoint Server folder at:


...\AgilePointServer\Tools\apsvrmon.exe

E.g. You could run the following command from the command prompt in the folder where the exe is located:

InstallUtil.exe apsvrmon.exe

AgilePoint Server Manager (Windows Service Environments)

The AgilePoint Server Manager is a sever management application that enables you to start, stop, add, delete, configure, and manage AgilePoint Server instances in a Windows Service environment.



Good to Know

• If you make changes to ports or SSL information on the AgilePoint Server Manager, you must run the Client Utility Tool against any affected web applications. This includes Enterprise Manager and SharePoint.

For more information, see Running the SVC Client Utility Tool.

Navigation

1. On the AgilePoint Server machine, click **Start > All Programs > AgilePoint > AgilePoint Server Manager**.

Field Definitions

Field Name	Definition	
Service Name	Definition: Specifies the name you want to use to identify the Windows service associated with the AgilePoint Server instance.	
	Allowed Values: A single line of text. Default Value: None	
Display Name	Definition: Specifies the name you want to display to users to identify the AgilePoint Server instance. Allowed Values: A single line of text. Default Value: None	
Location	Definition: Specifies the path to the AgilePoint Windows Service instance. Allowed Values: A valid absolute file path. Default Value: None	
WSHttp Port	Definition: A free, unique port AgilePoint Server can use for WSHttp binding. This field is required. Allowed Values: Specifies a valid WSHttpPort number.	

Field Name	Definition
	Default Value:
	None
TCP Port	Definition:
	Specifies a free, unique port AgilePoint Server can use for TCP binding.
	This field is required.
	Allowed Values:
	A valid TCP port number.
	Default Value:
	None
BasicHttp Port	Definition:
	A free, unique port AgilePoint Server can use for BasicHttp binding.
	This field is required.
	Allowed Values:
	A valid port number.
	Default Value:
	None
Web HTTP Port	Definition:
	Specifies a free, unique port AgilePoint Server can use for REST API calls.
	To access this field, click the Rest Port Information tab.
	Allowed Values:
	A valid HTTP port number.
	Default Value:
	None
Service Factory Binding	Definition:
	Specifies the path to the service factory binding.
	To access this field, click the Rest Port Information tab.
	Allowed Values:
	A valid path.

Field Name	Definition
	Default Value:
	Deselected
Use Secure Connection (SSL)	Definition:
	The common name (CN) or domain name or fully qualified domain name associated with your SSL certificate.
	To access this field, click the SSL Settings tab.
	Allowed Values:
	An appSettings key in the following format:
	Selected - SSL encryption is enabled.
	Deselected - SSL encryption is disabled.
	Default Value:
	Deselected
Domain Name	Definition:
	The common name (CN) or domain name or fully qualified domain name associated with your SSL certificate.
	To access this field, click the SSL Settings tab.
	Allowed Values:
	An appSettings key in the following format:
	A text string representing your common name or domain name.
	Default Value:
	None
	Example:
	mydomain.com
Check Availability of Ports	Function:
	Tests the specified ports to ensure they are free.
UserName	D. C. W.
	Definition:
	Specifies the user name for the AgilePoint service account.
	Allowed Values:
	A valid user name in the format domain\username.
	Default Value:

	Definition	
	None	
	Example:	
	MYDOMAIN\APServiceUser	
Password	Definition:	
	The password for the authentication account.	
	Allowed Values:	
	A valid password.	
	Default Value:	
	None	
Site	Definition:	
	Specifies the web site from the list you created for AgilePoint during pre-installation.	
	Allowed Values:	
	A valid web site name.	
	Default Value:	
	AgilePointWebsite	
/irtual Directory	Definition:	
	Specifies the name you want to use for the virtual directory that contains the files for the Enterprise Manager web application.	
	Allowed Values:	
	A valid virtual directory name.	
	The name EnterpriseManager is suggested.	
	Default Value:	
	None	
Application Pool	Definition:	
	Specifies the IIS application pool for the Enterprise Manager web application you want to run.	
	Allowed Values:	
	A valid application pool.	
	Default Value:	
	AgilePointAppPool	

Field Name	Definition
Add (±)	Creates a new AgilePoint Windows Service instance.
Start (▶)	Function: Starts the selected AgilePoint Windows Service instance.
Stop ()	Function: Stops the selected AgilePoint Windows Service instance.
Delete ()	Function: Deletes the selected AgilePoint Windows Service instance.
Refresh (₹)	Function: Refreshes the selected AgilePoint Windows Service instance.
Server Configuration (🍑)	Function: Opens the AgilePoint Server Configuration window for the selected AgilePoint Windows Service instance.
Enterprise Manager ()	Function: Opens Enterprise Manager for the selected AgilePoint Windows Service instance.
Update	Function: Saves changes to an AgilePoint Windows Service instance configuration.

Adding a Server Instance

To add a server instance, in AgilePoint Server Manager, click the **Add** button.

Deleting a Server Instance

To delete a server instance, in AgilePoint Server Manager, click the **Delete** button.

Starting a Server Instance

To start a server instance, in AgilePoint Server Manager, click the **Start** button.

Stopping a Server Instance

To stop a server instance, in AgilePoint Server Manager, click the **Stop** button.

Configuring a Server Instance

To configure a server instance, in AgilePoint Server Manager, click the **Configure** button. The AgilePoint Configuration window opens. Follow the instructions for the AgilePoint Server Configuration utility in this document.

Managing a Server Instance

To manage a server instance, in AgilePoint Server Manager, click the **Internet Explorer** icon. Enterprise Manager opens in Internet Explorer. Follow the instructions for Enterprise Manager in this document and the Enterprise Manager online help.

Running the SVC Client Utility Tool

Once you have upgraded to AgilePoint BPMS v5.0 R2, you must run the SVC Client Utility Tool on each instance of AgilePoint Enterprise Manager in your environment.

This topic provides the standard instructions for running the SVC Client Utility on any ASP.NET web application.

Prerequisites

- AgilePoint Server running in Windows Service mode.
- You have applied the AgilePoint BPMS v5.0 R2 upgrade on all applicable AgilePoint machines.
- You have updated your AgilePoint Server instances.
- Create a backup copy of the configuration file for the application you are configuring before using this utility.
- If you are using SharePoint or AgileForms Server on a machine that is not the AgilePoint Server machine (typically the case), copy the web.config file from the SharePoint or AgileForms machine to AgilePoint Server machine. The following are the default locations of the target web.config files:
 - SharePoint c:\inetpub\wwwroot\wss\VirtualDirectories\[port number]
 - AgileForms [AgileForms Server installation folder]\Webroot

Navigation

Do one of the following:

- 1. On the AgilePoint Server machine, navigate to [AgilePoint Server Installation]\SVCUtilityTool \AgilePointWindowsServiceClientUtilityTool.exe
- 2. Open the AgilePoint installation file, and click **Utilities and Other Support Files > AgilePoint Windows Service Client Utility Tool**.

Instructions

- 1. In the AgilePoint Windows Service Client Utility Tool dialog box, complete the following fields:
 - Service Address The URI for the Windows Service for which you are creating the binding. The
 information required to build this URI is provided in the AgilePoint Server Manager window.
 - HTTP http://[APServer Machine Name]: [Http Port]/AgilePointServer

When you create the bindings for the web application, the settings are automatically configured in the web.config file for both HTTP and TCP protocols. By default, the HTTP bindings are used. However, you can switch to TCP by modifying the following properties in the web.config:

Change the following so value="NetTcpBinding_IWCFWorkflowService"

```
<add key="WorkFlowBindingUsed" value="WSHttpBinding_IWCFWorkflowService" /
>
```

Change the following so value="NetTcpBinding_IWCFEventServices"

```
<add key="EventServicesBindingUsed"
value="WSHttpBinding IWCFEventServices" />
```

• Change the following so value="NetTcpBinding_IWCFAdminService" <add key="AdminBindingUsed" value="WSHttpBinding IWCFAdminService" />

- Target Config The file name and location of the configuration file for the application you are configuring. This is required for SharePoint Integration. For other applications, you only need to run this utility if you are prompted.
 - SharePoint Integration The web.config for the SharePoint web application you want to bind.
 - Enterprise Manager The web.config for the Enterprise Manager web application.
 - Data Services DataServicesWindowsService.exe.config in the Data Services installation folder.
 The default location is C:\Program Files\AgilePoint\AgilePoint\Data Services\
 - AgileForms The web.config file in the AgileForms installation folder. The default location is C: \Program Files\AgilePoint\AgileForms Server\Webroot
 - **Deployment Service** apds.exe.config file in the Deployment Service installation folder. The default location is C:\Program Files (x86)\AgilePoint\AgilePoint Deployment Service\
- 2. Click **Settings** to configure the following fields:
 - Max Buffer Size
 - Max Buffer Pool Size
 - Max Received Message Size
 - Max String Content Length
 - Max Array Length

Guidance for modifying these values can be found at the following articles on MSDN:

- http://msdn.microsoft.com/en-us/library/ms731361(v=VS.100).aspx
- http://msdn.microsoft.com/en-us/library/ms731325(v=VS.100).aspx

3. If you are using SharePoint or AgileForms Server on a machine that is not the AgilePoint Server machine, copy the modified web.config file back to its original location on the SharePoint or AgileForms Server machine.

Enabling SSL in AgilePoint Server Manager

To enable the SSL Settings in AgilePoint Server Manager, do the following.

Prerequisites

- You must have an SSL certificate. To create one, see Creating a Self-signed SSL Certificate
- Your certificate must be bound to AgilePoint Server. For more information, see Binding the SSL Certificate to AgilePoint Server Port

Navigation

1. On the AgilePoint Server machine, click Start > All Programs > AgilePoint > AgilePoint Server Manager.

Instructions

- On the AgilePoint Server Manager, select your AgilePoint Windows Service instance.
- On the SSL Settings tab, select Use secure connection (SSL).
- 3. On the **Domain Name** field, enter the common name or domain name for your SSL certificate.
- 4. Restart the AgilePoint Server instance.

Creating a Self-signed SSL Certificate

To create a self-signed SSL certificate, do the following.

Prerequisites

Microsoft Visual Studio installed.

Navigation

1. Click Start > All Programs > Visual Studio > Visual Studio Tools > Visual Studio Command Prompt.

Instructions

1. On the Visual Studio command prompt, enter the following command:

Makecert -sv SignRoot.pvk -cy authority -r signroot.cer -a sha1 -n "CN=[your certification name]" -ss my -sr localmachine

- 2. To move your SSL certificate from **Personal** folder to **Trusted Root Certificate Authorities** folder, complete the following steps:
 - a. In the Visual Studio command prompt, enter mmc.
 - b. On the Console Root window, click File > Add/Remove Snap-in.
 - c. On the Add or Remove Snap-ins window, select Certificates, and click Add.
 - d. On the **Certificates snap-in** window, click **Computer account**.
 - e. On the **Select Computer** window, click **Local computer**.

- f. On the Console Root window, click the Right arrow to expand Certificates (Local Computer)
- g. Drag your SSL certificate from the **Personal** folder to the **Trusted Root Certificate Authorities** folder.
- 3. To give your SSL certificate URL name, enter the following command:

Makecert -iv SignRoot.pvk -ic signroot.cer -cy end -pe -n CN="SSL-Url-Name" -eku 1.3.6.1.5.5.7.3.1 - ss my -sr localmachine -sky exchange -sp "Microsoft RSA SChannel Cryptographic Provider" -sy 12

More Information

http://msdn.microsoft.com/en-us/library/bfsktky3.aspx

Binding the SSL Certificate to AgilePoint Server Port

To bind the SSL Certificate to AgilePoint Server Port, do the following.

Prerequisites

- AgilePoint Server installed on premises in Windows Service mode.
- The ports you use for binding in AgilePoint Server. You can find these in AgilePoint Server Manager.
- You must have an SSL certificate. To create one, see Creating a Self-signed SSL Certificate

Navigation

1. Click Start > All Programs > Visual Studio > Visual Studio Tools > Visual Studio Command Prompt.

Instructions

- 1. In the Visual Studio command prompt, enter **mmc**.
- On the Console Root window, click File > Add/Remove Snap-in.
- On the Add or Remove Snap-ins window, select Certificates, and click Add.
- On the Certificates snap-in window, click Computer account.
- 5. On the **Select Computer** window, click **Local computer**.
- 6. On the Console Root window, click the Right arrow to expand Certificates (Local Computer)
- 7. Click the **Right arrow** to expand **Personal** folder.
- 8. Right-click the **Certificates** folder.
- 9. Select All Task > Import.
- 10. On the Certificates Import wizard, click the Next button.
- 11. In the **File name** field, browse your SSL certificate.
- 12. Double-click your SSL certificate.
- Select the **Details** tab.
- 14. In the shown field, select ALL.
- 15. Select **Thumbprint**.
- 16. Copy the value of the thumbprint.

17. On the Visual Studio command prompt, enter the following command:

 $netsh\ http\ add\ sslcert\ ipport=0.0.0.0: portnumber\ certhash=SSL-Certificate-thumbprint-value-without-spaces\ appid=\{c929c857-e10a-48c4-b123-5713faba528e\}$